# APPENDIX J TRANSACTION FORMATS

#### **APPENDIX J**

#### **Transaction Formats**

The following 53 tables represent all of the Standard Army Retail Supply System-Gateway's (SARSS-GW's) transaction formats.

**NOTE**: Objective Supply Capability (OSC) has undergone a name change and is now called SARSS-GW. All references to OSC and gateway have been changed or refer to SARSS-GW.

<u>Table</u>		<u>Page</u>
J-1	SARSS-GW-Created DS4 ASL Requisition to DAAS	
J-2	ULLS or SAMS-1 Dedicated Passing Action to DAAS	
J-3	DS4, ULLS, and SAMS-1 Passing Action to SAILS	J-14
J-4	GS Reparable Replenishment to DAAS	J-19
J-5	AIMI Replenishment to DAAS	
J-6	ULLS or SAMS-1 Passing Action to SARSS	J-25
J-7	ULLS or SAMS-1 Non-Dedicated Passing Action to DAAS	J-26
J-8	DS4 Passing Action to Supporting SARSS2AC/B	
J-9	DS4, ULLS, or SAMS-1 Passing Action to DAAS (First Denial)	
J-10	DS4 Passing Action to DAAS	
J-11	Manager Entry Code (MEC) 8 to SAILS (DS4 ASL Replenishment)	
J-12	Manager Entry Code (MEC) 8 to SAILS (Passing Action to DAAS)	J-43
J-13	Manager Entry Code (MEC) 8 to SAILS (Referral Order to a	
	Nonsupporting DS4 or SAILS)	J-45
J-14	GS Reparable Manager Entry Code (MEC) 8 to SAILS	
J-15	AIMI Replenishment Manager Entry Code (MEC) 8 to SAILS	
J-16	Manager Entry Code (MEC) 5 to SAILS (GS Reparable Requisition)	
J-17	AIMI Manager Entry Code (MEC) B to SAILS	
J-18	Update Transaction to DS4 (DS4 ASL Requisition to DAAS)	
J-19	Update Transaction to DS4 (DS4 ASL Replenishment to DAAS)	J-63
J-20	Update Transaction to DS4 (Passing Action to DAAS or SAILS,	
	Referral Order to a Nonsupporting DS4 or SAILS, or SAILS	
	Due-Out for GS Reparable and AIMI)	J-67
J-21	A4_ Dedicated Referral Order to a DS4 or SAILS	
J-22	A4_ Non-Dedicated Referral Order to a DS4 or SAILS	
J-23	A4_ Dedicated Referral Order to a SARSS1	
J-24	A4_ Non-Dedicated Referral Order to a SARSS1	
J-25	A4_ Referral Order to a SARSS1	
J-26	A4_ Referral Order to SAILS or DS4	J-91

<u>Table</u>		<u>Page</u>
J-27	A4_ Referral Order to a SAILS or DS4 to Satisfy an A0_ from SARSS2AC/B	. J-92
J-28	Supply Status Transaction to DS4	. J-93
J-29	Supply Status Transaction to DS4 (Answer to Follow-Up)	
J-30	Status Transaction for ULLS or SAMS-1 Passing Action to DAAS	
J-31	AE1 with BA Status Transaction from DS4 or SAILS Passed to SARSS2AC/B	
J-32	AE1 with BH Status Transaction from DS4 or SAILS Passed as a BA Status to SARSS2AC/B	
J-33	AE1 with CB Status Transaction Blank Suffix Code (Refusal) or Suffix Code not Blank (First Denial) from DS4 or A4_ 1R or 1S from SAILS Passed as a BM Status to SARSS2AC/B	
J-34	AE1 with CB Status Transaction (First Denial) from DS4 or an A4_ 1R or 1S from SAILS Passed as a C* Status to SARSS2AC/B	J-102
J-35	AE1 with CB Status Transaction (Subsequent Denial) from DS4 or an A4_ 1R or 1S from SAILS Passed as a CM Status to SARSS2AC/B	J-104
J-36	SARSS-GW-Created AE1 Status Transaction Answer to an AC_ or AK_ from SARSS2AC/B and Downloaded to SARSS2AC/B	
J-37	SARSS-GW-Created AE1 Status Transaction Answer to an AC_ or AK_ from SARSS2AC/B and Downloaded to SARSS2AC/B (AC_ or AK_ Reformatted and Uploaded to DAAS)	
J-38	SARSS-GW-Created AE1 Status Transaction Answer to an AM_ from SARSS2AC/B and Downloaded to SARSS2AC/B	
J-39	SARSS-GW-Created AE1 Status Transaction Answer to an AM_ from SARSS2AC/B and Downloaded to SARSS2AC/B (AM_	
J-40	Reformatted and Uploaded to DAAS)	
	AT_ from SARSS and Downloaded to SARSS2B	
J-41	Status Transaction for A4_ Dedicated Referral to Another Activity	. J-111
J-42	AC_ or AK_ in Conjunction with an AC_ or AK_ from SARSSAC/B and Reformatted by SARSS-GW and Uploaded to DAAS	J-112
J-43	AM_ in Conjunction with an AM_ from SARSS2AC/B and	1 4 4 0
	Reformatted and Uploaded to DAAS	
J-44	AS1 Created from BA Status Transaction Passed to SARSS2AC/B	J-114
J-45	SARSS-GW-Created AS_ Shipment Status Transaction Answer to an AF_ or AT_ from SARSS and Downloaded to SARSS2B	J-115
J-46	YAM SARSS Due-In/Dedicated Due-In Transaction for a DS4, ULLS, or SAMS-1 Referral Action to Another Activity	J-116
J-47	YDO to a SARSS-1 (Response for Referral)	
J-48	YAL Due-In and Due-Out Transaction for a Referral Action to Another Activity	
	· • • . · · · · · · · · · · · ·	

<u>Table</u>		<u>Page</u>
J-49	Demand Transaction (DHA) SAILS (Referral Order to a	
	Nonsupporting SAILS)	J-127
J-50	ABF Extract Record from SAILS or DS4	J-128
J-51	ABF Extract Record from SARSS (YSB)	J-130
J-52	SARSS-GW-Created YIC Due-In from a Retrograde Transaction	J-132
J-53	SARSS-GW-Created DIC YIL Follow-Up to Retrograde Shipment	
	Transaction	J-133
	ransaction	J-133

Table J-1
SARSS-GW-Created DS4 ASL Requisition to DAAS
(Unit-Level Logic)

(Unit-Level Logic)			
Data Element	Record Pos.	Definition/Source	
DIC	1-3	<ul> <li>a. In CONUS, SARSS-GW perpetuates this value from the source A0 See Note 1.</li> <li>b. In OCONUS, if the value in the conus_oconus field of the supporting DSU's abf_xref_tab is O, SARSS-GW converts RP 3 as follows:</li> <li>A to 1  B to 2  D to 4  E to 5</li> </ul>	
RIC	4-6	SARSS-GW enters the value from the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0	
Media and Status Code	7	SARSS-GW enters the value from the media_cd_wh field of the supporting SAILS' abf_xref_tab.	
NSN, UI, and Quantity	8-29	SARSS-GW perpetuates these values from the source A0	
DODAAC	30-35	SARSS-GW enters the unit's prime support DSU DODAAC from the dsu_a, dsu_f, dsu_h, or dsu_k fields of the supporting DSU's abf_xref_tab for the stock number in RP 8-22 of the source A0 See Note 2.	
Date	36-39	SARSS-GW enters the current date as YDDD.	
Serial number	40-43	SARSS-GW uses the docreg field of the supporting DSU's dodaac_tab to determine the serial number value as follows:	
		RP 40 is X. RP 41-43 is the next sequence number, beginning with 001 each day.	
Demand Code	44	SARSS-GW perpetuates this value from the source A0	
Supplementary address	45-50	SARSS-GW enters this value from the ds_supp_addr field of the instln_tab.	

Table J-1 (Cont.)				
SARSS-GW-Created DS4 ASL Requisition to DAAS (Unit-Level Logic)				
Data Element	Record Pos.	Definition/Source		
Signal Code	51	<ul> <li>a. SARSS-GW enters the value from the sig_asl_stock field of the abf_xref_tab if RP 2 of the matcat field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is 2 or not 2 and the first position of the SOS field of the amdf_tab for that stock number is not A, B, or C.</li> <li>b. SARSS-GW enters the value from the sig_asl_pa field of the abf_xref_tab if RP 2 of the matcat field of the amdf_tab for that stock number is not 2 and the first position of the SOS field of the amdf_tab for that stock number is A, B, or C.</li> </ul>		
Fund Code	52-53	<ul> <li>a. SARSS-GW enters the value from the fc_ext_* field of the msc_tab if RP 2 of the matcat field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is a number or a letter and the first position of the SOS field of the amdf_tab for that stock number is not A, B, or C.</li> <li>b. SARSS-GW enters the value GA if RP 2 of the matcat field of the amdf_tab is a letter and the first position of the SOS field of the amdf_tab for that stock</li> </ul>		
		number is A, B, or C.		
Distribution Code	54	SARSS-GW enters the value from the distr_cd of the supporting SAILS' abf_xref_tab.		
	55-56	These positions remain blank.		
Project Code, Priority, RDD, and Advice Code	57-66	SARSS-GW perpetuates these values from the source A0		
	67-79	These positions remain blank.		
SARSS-GW Code	80	SARSS-GW enters X. See Note 3.		

Table J-1 (Cont.) SARSS-GW-Created DS4 ASL Requisition to DAAS (Unit-Level Logic)

#### Notes:

- 1. The source A0\_ is the one SARSS-GW received from an ULLS or SAMS-1 and for which it is creating an ASL requisition for the supporting DSU.
- 2. SARSS-GW determines the transaction DODAAC using one of three methods.
- a. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SIC value from the sic field of the abf\_tab as follows:

SIC	DSU Code	Supporting DODAAC
Α	F	ssa_ixa
С	Α	ssa_ixc
F	K	ssa_iv
J	K	ssa_iii
M	Н	ssa_ixm
T	K	ssa_vii
U	K	ssa_ii_x

b. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV and the sic field is blank or there is no abf\_tab record, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by converting the value in the scmc field of the amdf\_tab to a SIC value. SARSS-GW then converts the SIC value to a DSU Code as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	SIC	DSU Code	Supporting DODAAC
(1st pos.)  1 2 3 4 5 6 7 8 9 9	Anything A	UTJFUUTCAMCU	K K K K K K A F H A K	ssa_i_vi ssa_ii_x ssa_iii ssa_iv ssa_v ssa_i_vi ssa_vii ssa_viii ssa_ixa ssa_ixm ssa_ixc ssa_i_x
•	,,g	•	• •	555X

Table J-1 (Cont.)
SARSS-GW-Created DS4 ASL Requisition to DAAS
(Unit-Level Logic)

Notes: (Cont.)

c. If the typ field of the abf\_xref\_tab for the supporting SSA is not DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SCMC value from the amdf\_tab for the stock number in RP 8-22 as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting DODAAC
1	Anything	ssa_i_vi
2	Anything	ssa_ii_x
3	Anything	ssa_iii
4	Anything	ssa_iv
5	Anything	ssa_v
6	Anything	ssa_i_vi
7	Anything	ssa_vii
8	Anything	ssa_viii
9	Α	ssa_ixa
9	L	ssa_ixm
9	Not A or L	ssa_ixc
0	Anything	ssa_ii_x

3. This entry is required to track SARSS-GW-generated requisitions.

Table J-2
ULLS or SAMS-1 Dedicated Passing Action to DAAS
(Response Code 14)
(Unit-Level Logic)

	1	
Data Element	Record Pos.	Definition/Source
DIC	1-3	a. In CONUS, SARSS-GW perpetuates this value from the source A0 See Note 1.
		b. In OCONUS, if the value in the conus_oconus field of the supporting SSA's abf_xref_tab equals O, SARSS-GW converts RP 3 as follows:
		A to 1 B to 2 D to 4 E to 5
RIC	4-6	SARSS-GW enters the value from the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0
Media and Status Code	7	SARSS-GW enters the value from the media_cd_nsl_wh field of the supporting SSA's abf_xref_tab. See Note 2.
FSC	8-11	SARSS-GW perpetuates this value from the source A0_ if it matches the amdf_tab. If it does not match, SARSS-GW applies the correct FSC from the amdf_tab.
NIIN, UI, Quantity, DODAAC, date, SN, and Demand Code	12-44	SARSS-GW perpetuates these values from the source A0
Supplementary address	45-50	SARSS-GW enters the user's prime support SSA DODAAC. See Note 3.

Table J-2 (Cont.)
ULLS or SAMS-1 Dedicated Passing Action to DAAS
(Response Code 14)
(Unit-Level Logic)

(91111 20101 20910	(OTHE EGVOT EGGIO)		
Data Element	Record Pos.	Definition/Source	
Signal Code	51	<ul> <li>a. If the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not A, B, or C, SARSS-GW enters the value from the sig_ded_funded field of the requesting activity's dodaac_tab, or if the sig_ded_funded field is blank, SARSS-GW enters the value from the sig_nsl_stock field of the supporting SSA's abf_xref_tab.</li> <li>b. If the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is A, B, or C, SARSS-GW enters the value from the sig_ded_funded field of the requesting activity's dodaac_tab if the second position of the matcat field of the amdf_tab is 2, or if the sig_ded_funded field is blank, SARSS-GW enters the value from the sig_nsl_stock field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is 2.</li> <li>c. If the first position of the SOS field of the amdf_tab</li> </ul>	
		for the stock number in RP 8-22 of the source A0_ is A, B, or C, SARSS-GW enters the value from the sig_ded_pa field of the requesting activity's dodaac_tab if the second position of the matcat field of the amdf_tab is not 2, or if the sig_ded_pa field is blank, SARSS-GW enters the value from the sig_nsl_pa field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is not 2.	

Table J-2 (Cont.)
ULLS or SAMS-1 Dedicated Passing Action to DAAS
(Response Code 14)
(Unit-Level Logic)

(Offit-Level Logic)			
Data Element	Record Pos.	Definition/Source	
Fund Code	52-53	<ul> <li>a. SARSS-GW enters the value from the fc_ext_1 field of the requesting activity's msc_tab if the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not A, B, or C.</li> <li>b. SARSS-GW enters the value from the fc_ext_1 field of the requesting activity's msc_tab if the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is A, B, or C and the second position of the matcat field is numeric.</li> <li>c. SARSS-GW enters the value GA if the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is A, B, or C and the second position of the matcat field is not numeric.</li> </ul>	
Distribution Code	54	SARSS-GW enters the value from the distr_cd field of the supporting SSA's abf_xref_tab.	
	55-56	These positions remain blank.	
Project Code, Priority, RDD, and Advice Code	57-66	SARSS-GW perpetuates these values from the source A0	
	67-79	These positions remain blank.	
SARSS-GW Code	80	SARSS-GW enters X.	

Table J-2 (Cont.)
ULLS or SAMS-1 Dedicated Passing Action to DAAS
(Response Code 14)
(Unit-Level Logic)

#### Notes:

- 1. The source A0 is the one SARSS-GW received from ULLS, SAMS-1, or DS4.
- 2. The supporting SSA from the dodaac\_tab for the DODAAC in RP 30-35 is determined by the aimi\_tab if the NIIN in RP 12-22 matches an entry and the intermediate support is SARSS, or by the first two positions of the SCMC field of the amdf\_tab for the NIIN in RP 12-22 as follows:
- a. If the NIIN in RP 12-22 matches an entry on the aimi\_tab and the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is not blank, SARSS-GW uses the spt\_ric\_aimi SSA ABF.
- b. If the NIIN in RP 12-22 matches an entry on the aimi\_tab but the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is blank, or the NIIN in RP 12-22 does not match an entry on the aimi\_tab, SARSS-GW uses the first two positions of the scmc field of the amdf\_tab for the NIIN in RP 12-22 to determine the supporting SSA ABF as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting SSA ABF
1 2 3 4 5 6 7 8 9 9	Anything A	spt_ric_i_vi spt_ric_ii_x spt_ric_iii spt_ric_iv spt_ric_v spt_ric_vii spt_ric_viii spt_ric_ixa spt_ric_ixm spt_ric_ixc spt_ric_ixc spt_ric_ii_x

Table J-2 (Cont.)
ULLS or SAMS-1 Dedicated Passing Action to DAAS
(Response Code 14)
(Unit-Level Logic)

Notes: (Cont.)

- 3. SARSS-GW determines the transaction DODAAC using one of three methods.
- a. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SIC value from the sic field of the abf\_tab as follows:

DSU	Supporting
Code	DODAAC
F	ssa_ixa
Α	ssa_ixc
K	ssa_iv
K	ssa_iii
Н	ssa_ixm
K	ssa_vii
K	ssa_ii_x
	Code F A K K H

b. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV and the sic field is blank or there is no abf\_tab record, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by converting the value in the scmc field of the amdf\_tab to a SIC value. SARSS-GW then converts the SIC value to a DSU Code as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	SIC	DSU Code	Supporting DODAAC
1	Anything	U	K	ssa_i_vi
2	Anything	I	K	ssa_ii_x
3	Anything	J	K	ssa_iii
4	Anything	F	K	ssa_iv
5	Anything	U	K	ssa_v
6	Anything	U	K	ssa_i_vi
7	Anything	T	K	ssa_vii
8	Anything	С	Α	ssa_viii
9	Α	Α	F	ssa_ixa
9	L	M	Н	ssa_ixm
9	Not A or L	С	Α	ssa_ixc

Table J-2 (Cont.)
ULLS or SAMS-1 Dedicated Passing Action to DAAS
(Response Code 14)
(Unit-Level Logic)

0 Anything U K ssa\_ii\_x

Notes: (Cont.)

c. If the typ field of the abf\_xref\_tab for the supporting SSA is not DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SCMC value from the amdf\_tab for the stock number in RP 8-22 as follows:

	SCMC 1st pos.)	SCMC (2nd pos.)	Supporting DODAAC
1		Anything	ssa_i_vi
2	2	Anything	ssa_ii_x
3	3	Anything	ssa_iii
4	1	Anything	ssa_iv
5	5	Anything	ssa_v
6	6	Anything	ssa_i_vi
7	7	Anything	ssa_vii
8	3	Anything	ssa_viii
9	)	Α	ssa_ixa
9	)	L	ssa_ixm
9	)	Not A or L	ssa_ixc
C	)	Anything	ssa_ii_x

Table J-3
DS4, ULLS, and SAMS-1 Passing Action to SAILS
(DS- and Unit-Level Logic)

(DS- and Unit-Lev	/ei Logic)	
Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW perpetuates this value from the source A0 See Note 1.
RIC	4-6	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.
		b. If it is blank, SARSS-GW enters the value from the ric field of the supporting sails abf_xref_tab.
Media and Status Code	7	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.
		b. If it is blank, SARSS-GW enters the value from the media_cd_nsl field of the supporting DSU's abf_xref_tab.
NSN, UI, Quantity, DODAAC, Date, SN, and Demand Code	8-44	SARSS-GW perpetuates these values from the source A0 See Note 2.
Supplementary address	45-50	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.
		b. If it is blank, SARSS-GW enters the user's prime support DSU DODAAC from the ssa_* field of the supporting DSU's abf_xref_tab for the stock number in RP 8-22. See Note 3.

Table J-3 (Cont.) DS4, ULLS, and SAMS-1 Passing Action to SAILS (DS- and Unit-Level Logic)				
Data Element	Record Pos.	Definition/Source		
Fund Code,	52-66	<ul> <li>a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.</li> <li>b. If it is blank and the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not A, B, or C, SARSS-GW enters the value from the sig_ded_funded field of the requesting activity's dodaac_tab, or if the sig_ded_funded field is blank, SARSS-GW enters the value from the sig_nsl_stock field of the supporting SSA's abf_xref_tab.</li> <li>c. If it is blank and the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 is A, B, or C, SARSS-GW enters the value from the sig_ded_funded field of the requesting activity's dodaac_tab if the second position of the matcat field of the amdf_tab is 2, or if the sig_ded_funded field is blank, SARSS-GW enters the value from the sig_nsl_stock field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is 2.</li> <li>d. If it is blank and the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 is A, B, or C, SARSS-GW enters the value from the sig_ded_pa field of the requesting activity's dodaac_tab if the second position of the matcat field of the amdf_tab is not 2, or if the sig_ded_funded field is blank, SARSS-GW enters the value from the sig_nsl_pa field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is not 2.</li> <li>SARSS-GW perpetuates these values.</li> </ul>		
Distribution Code, Project Code, Priority, RDD, and Advice Code	32-00	SANOS-OW perpetuates triese values.		
	67-74	These positions are blank.		
APC	75-78	SARSS-GW perpetuates this value from the source A0		
	79-80	These positions are blank.		

Table J-3 (Cont.)

DS4, ULLS, and SAMS-1 Passing Action to SAILS

(DS- and Unit-Level Logic)

#### Notes:

- 1. The source A0\_ is the one SARSS-GW received from ULLS, SAMS-1, or DS4.
- 2. The supporting SSA from the dodaac\_tab for the DODAAC in RP 30-35 is determined by the aimi\_tab if the NIIN in RP 12-22 matches an entry and the intermediate support is SARSS, or by the first two positions of the SCMC field of the amdf\_tab for the NIIN in RP 12-22 as follows:
- a. If the NIIN in RP 12-22 matches an entry on the aimi\_tab and the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is not blank, SARSS-GW uses the spt\_ric\_aimi SSA ABF.
- b. If the NIIN in RP 12-22 matches an entry on the aimi\_tab but the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is blank, or the NIIN in RP 12-22 does not match an entry on the aimi\_tab, SARSS-GW uses the first two positions of the scmc field of the amdf\_tab for the NIIN in RP 12-22 to determine the supporting SSA ABF as follows:

SCMC (2nd pos.)	Supporting SSA ABF
Anything	spt_ric_i_vi
, ,	spt_ric_ii_x
	spt_ric_iii spt_ric_iv
, ,	spt_ric_v
Anything	spt_ric_i_vi
Anything	spt_ric_vii
Anything	spt_ric_viii
Α	spt_ric_ixa
L	spt_ric_ixm
Not A or L	spt_ric_ixc
Anything	spt_ric_ii_x
	(2nd pos.)  Anything A

Table J-3 (Cont.)

DS4, ULLS, and SAMS-1 Passing Action to SAILS

(DS- and Unit-Level Logic)

Notes: (Cont.)

3. SARSS-GW determines the transaction DODAAC using one of three methods.

a. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SIC value from the sic field of the abf\_tab as follows:

SIC	DSU Code	Supporting DODAAC
Α	F	ssa_ixa
С	Α	ssa_ixc
F	K	ssa_iv
J	K	ssa_iii
M	Н	ssa_ixm
Τ	K	ssa_vii
U	K	ssa_ii_x

b. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV and the sic field is blank or there is no abf\_tab record, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by converting the value in the scmc field of the amdf\_tab to a SIC value. SARSS-GW then converts the SIC value to a DSU Code as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	SIC	DSU Code	Supporting DODAAC	
1	Anything	U	K	ssa_i_vi	
2	Anything	Т	K	ssa_ii_x	
3	Anything	J	K	ssa_iii	
4	Anything	F	K	ssa_iv	
5	Anything	U	K	ssa_v	
6	Anything	U	K	ssa_i_vi	
7	Anything	T	K	ssa_vii	
8	Anything	С	Α	ssa_viii	
9	Α	Α	F	ssa_ixa	
9	L	M	Н	ssa_ixm	
9	Not A or L	С	Α	ssa_ixc	
0	Anything	U	K	ssa_ii_x	

Table J-3 (Cont.)

DS4, ULLS, and SAMS-1 Passing Action to SAILS

(DS- and Unit-Level Logic)

Notes: (Cont.)

c. If the typ field of the abf\_xref\_tab for the supporting SSA is not DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SCMC value from the amdf\_tab for the stock number in RP 8-22 as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting DODAAC
1	Anything	ssa_i_vi
2	Anything	ssa_ii_x
3	Anything	ssa_iii
4	Anything	ssa_iv
5	Anything	ssa_v
6	Anything	ssa_i_vi
7	Anything	ssa_vii
8	Anything	ssa_viii
9	Α	ssa_ixa
9	L	ssa_ixm
9	Not A or L	ssa_ixc
0	Anything	ssa_ii_x

Table J-4
GS Reparable Replenishment to DAAS
(DS- and Unit-Level Logic [Non-SARSS])

(DS- and Unit-Level Logic [Non-SARSS])			
Data Element	Record Pos.	Definition/Source	
DIC	1-3	<ul> <li>a. In CONUS, SARSS-GW perpetuates this value from the source A0 See Note 1.</li> <li>b. In OCONUS, if the value in the conus_oconus field of the supporting DSU's abf_xref_tab is O, SARSS-GW converts RP 3 as follows:</li> <li>A to 1 B to 2 D to 4 E to 5</li> </ul>	
RIC	4-6	SARSS-GW enters the value from the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0	
Media and Status Code	7	SARSS-GW enters the value from the media_cd_wh field of the supporting SAILS' abf_xref_tab.	
NSN, UI, and Quantity	8-29	SARSS-GW perpetuates these values from the source A0	
DODAAC	30-35	SARSS-GW enters the value from the ssa_gsmt field of the supporting SAILS' abf_xref_tab.	
Date	36-39	SARSS-GW enters the current date as YDDD.	
Serial	40-43	SARSS-GW uses the docreg field of the supporting SAILS' dodaac_tab to determine the serial number value as follows:  RP 40 is X. RP 41-43 is the next available sequence number, beginning with 001 each day.	
Demand Code	44	SARSS-GW enters the value from the demand_cd field of the instln_tab.	
Supplementary address	45-50	SARSS-GW enters the value from the sails_gs_a_suppl, sails_gs_c_suppl, or sails_gs_m_suppl field of the supporting SAILS' abf_xref_tab if the stock number in RP 8-22 of the source A0_ is aircraft, common, or missile.	

Table J-4 (Cont.)				
GS Reparable Replenishment to DAAS				
(DS- and Unit-Lev	vel Logic [l	Non-SARSS])		
Data Element	Record Pos.	Definition/Source		
Signal Code	51	a. SARSS-GW enters the value from the sig_gs_stock field of the abf_xref_tab if RP 2 of the matcat field of the amdf_tab for the stock number is 2 or not 2 and the first position of the SOS field of the amdf_tab for that stock number is not A, B, or C.		
		b. SARSS-GW enters the value from the sig_gs_pa field of the abf-xref_tab if RP 2 of the matcat field of the amdf_tab for that stock number is not 2 and the first position of the SOS field of the amdf_tab for that stock number is A, B, or C.		
Fund Code	52-53	a. SARSS-GW enters the value from the fc_ext_* field of the msc_tab if RP 2 of the matcat field of the amdf_tab for the stock number is a number or letter and the first position of the SOS field of the amdf_tab for that stock number is not A, B, or C.		
		b. SARSS-GW enters the value GA if RP 2 of the matcat field of the amdf_tab is a letter and the first position of the SOS field of the amdf_tab for that stock number is A, B, or C.		
Distribution Code	54	SARSS-GW enters the value from the distr_cd field of the supporting SAILS' abf_xref_tab.		
	55-56	These positions remain blank.		
Project Code, Priority, RDD, and Advice Code	67-66	SARSS-GW perpetuates these values from the source A0		
	67-79	These positions remain blank.		
SARSS-GW Code	80	SARSS-GW enters X. See Note 2.		

Table J-4 (Cont.)
GS Reparable Replenishment to DAAS
(DS- and Unit-Level Logic [Non-SARSS])

#### General:

- 1. This transaction establishes a requirement at the commodity command if GS reparable assets on the installation are unavailable to fill requirements submitted to SARSS-GW.
- 2. CreatReparRepReq is the SARSS-GW application that creates this transaction.

#### Notes:

- 1. The source A0\_ is the one SARSS-GW received from ULLS or SAMS-1 for a GS reparable, or from DS4 for a DS reparable. SARSS-GW creates a transaction to replenish the GS reparable ASL.
- 2. This entry is required to track SARSS-GW-generated transactions.

Table J-5 AIMI Replenishment to DAAS				
(DS- and Unit-Lev	(DS- and Unit-Level Logic [Non-SARSS])			
Data Element	Record Pos.	Definition/Source		
DIC	1-3	<ul> <li>a. In CONUS, SARSS-GW perpetuates this value from the source A0 See Note 1.</li> <li>b. In OCONUS, if the value in the conus_oconus field of the supporting DSU's abf_xref_tab is O, SARSS-GW converts RP 3 as follows:</li> <li>A to 1  B to 2  D to 4  E to 5</li> </ul>		
RIC	4-6	SARSS-GW enters the value from the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0		
Media and Status Code	7	SARSS-GW enters the value from the media_cd_asl_wh field of the abf_xref_tab.		
NIIN, UI, and Quantity	8-29	SARSS-GW perpetuates these values from the source A0		
DODAAC	30-35	SARSS-GW enters the value from the ssa_aimi field of the abf_xref_tab.		
Date	36-39	SARSS-GW enters the current date as YDDD.		
Serial number	40-43	SARSS-GW uses the docreg field of the supporting SAILS' dodaac_tab to determine the serial number value as follows:  RP 40 is X. RP 41-43 is the next available sequence number, beginning with 001 each day.		
Demand Code	44	SARSS-GW enters the value from the aimi_demand_cd field of the instln_tab.		
Supplementary address	45-50	SARSS-GW enters the value from the sails_gs_a_suppl field of the abf_xref_tab.		

Table J-5 (Cont.) AIMI Replenishme	ent to DAA	S	
(DS- and Unit-Level Logic [Non-SARSS])			
Data Element	Record	Definition/Source	
	Pos.		
Signal Code	51	a. SARSS-GW enters the value from the sig_aimi_stock field of the abf_xref_tab if RP 2 of the matcat field of the amdf_tab is 2 or not 2 and the first position of the SOS field of the amdf_tab for that stock number is not A, B, or C.	
		b. SARSS-GW enters the value from the sig_aimi_pa field of the abf_xref_tab if RP 2 of the matcat field of the amdf_tab is not 2 and the first position of the SOS field of the amdf_tab for that stock number is A, B, or C.	
Fund Code	52-53	<ul> <li>a. SARSS-GW enters the value from the fc_ext_* field of the msc_tab if RP 2 of the matcat field of the amdf_tab for the stock number in RP 8-22 is a number or letter and the first position of the SOS field of the amdf_tab for that stock number is not A, B, or C.</li> <li>b. SARSS-GW enters the value GA if RP 2 of the matcat field of the amdf_tab is a letter and the first position of the SOS field of the amdf_tab for that stock number is A, B, or C.</li> </ul>	
Distribution Code	54	SARSS-GW enters the value from the distr_cd field of the supporting SAILS' abf_xref_tab.	
	55-56	These positions remain blank.	
Project Code	57-59	SARSS-GW enters the value from the aimi_project_cd field of the instln_tab.	
Priority, RDD, and Advice Code	60-66	SARSS-GW perpetuates these values from the source A0	
	67-79	These positions remain blank.	
SARSS-GW Code	80	SARSS-GW enters X. See Note 2.	

Table J-5 (Cont.)
AIMI Replenishment to DAAS
(DS- and Unit-Level Logic [Non-SARSS])

#### General:

- 1. This transaction establishes a requirement at the commodity command if GS reparable assets on the installation are unavailable to fill requirements submitted to SARSS-GW.
- 2. CreatReparRepReq is the SARSS-GW application that creates this transaction.

#### Notes:

- 1. The source A0\_ is the one SARSS-GW received from ULLS or SAMS-1 for a GS reparable, or from DS4 for a DS reparable. SARSS-GW creates a transaction to replenish the GS reparable ASL.
- 2. This entry is required by the Response Codes to track SARSS-GW-generated transactions.

Table J-6
ULLS or SAMS-1 Passing Action to SARSS
(Response Code 12)
(Unit-Level Logic)

(31111 20101 20910)		
Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW perpetuates this value from the source A0 See Note.
RIC	4-6	These positions remain blank.
Media and Status Code	7	SARSS-GW perpetuates this value from the source A0
FSC	8-11	SARSS-GW perpetuates this value from the source A0_ if it matches the amdf_tab. If it does not match, SARSS-GW applies the correct FSC from the amdf_tab.
Media and Status Code, NSN, UI, Quantity, DODAAC, Date, SN, Demand Code, Supplementary address, Signal Code, Fund Code, Distribution Code, Project Code, Priority, RDD, Advice Code, and SARSS-GW Code	7-80	SARSS-GW perpetuates these values from the source A0
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from the com_ric_ds field of the unit's DODAAC Table.

General: This transaction is formatted and downloaded to the prime supporting SARSS1 because assets were found at the supporting SARSS1 or at another SARSS1 supported by the same SARSS2AC/B.

Note: The source A0\_ is the one SARSS-GW received from ULLS or SAMS-1.

Table J-7
ULLS or SAMS-1 Non-Dedicated Passing Action to DAAS
(Response Code 14)
(Unit-Level Logic)

Data Flament	Docard	Definition/Course	
Data Element	Record Pos.	Definition/Source	
DIC	1-3	a. In CONUS, SARSS-GW perpetuates this value from the source A0 See Note 1.	
		b. In OCONUS, if the value in the conus_oconus field of the supporting SSA's abf_xref_tab is O, SARSS-GW converts RP 3 as follows:	
		A to 1 B to 2 D to 4 E to 5	
RIC	4-6	SARSS-GW enters the value from the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0	
Media and Status Code	7	SARSS-GW enters the value from the media_cd_asl_wh field of the supporting SSA's abf_xref_tab. See Note 2.	
FSC	8-11	SARSS-GW perpetuates this value from the source A0_ if it matches the amdf_tab. If it does not match, SARSS-GW applies the correct FSC from the amdf_tab.	
NIIN, UI, and Quantity	12-29	SARSS-GW perpetuates these values from the source A0	
DODAAC	30-35	SARSS-GW enters the user's prime support SSA DODAAC. See Note 3.	
Date	36-39	SARSS-GW enters the date as YDDD.	
Serial number	40-43	SARSS-GW uses the docreg field of the supporting SSA's dodaac_tab to determine what serial number to enter as follows:	
		RP 40 is X, V, or X. RP 41-43 is the next available sequence number, beginning with 001 each day.	
Demand Code	44	SARSS-GW perpetuates this value from the source A0	

Table J-7 (Cont.)
ULLS or SAMS-1 Non-Dedicated Passing Action to DAAS
(Response Code 14)
(Unit-Level Logic)

<u> </u>			
Data Element	Record Pos.	Definition/Source	
Supplementary address	45-50	<ul> <li>a. SARSS-GW enters Y in RP 45.</li> <li>b. SARSS-GW enters Y in RP 46 if the SLC on the supporting ABF for the stock number in RP 8-22 is not Z. If it is Z, SARSS-GW enters W.</li> <li>c. SARSS-GW enters W in RP 47.</li> <li>d. Positions 48-49 are blank.</li> </ul>	
Signal Code	51	<ul> <li>a. If the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not A, B, or C, SARSS-GW enters the value from the sig_sa_asl_stock field of the supporting SSA's abf_xref_tab.</li> <li>b. If the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is A, B, or C, SARSS-GW enters the value from the sig_sa_asl_stock field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is a number.</li> <li>c. If the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is A, B, or C, SARSS-GW enters the value from the sig_sa_nsl_pa field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is a letter.</li> </ul>	

Table J-7 (Cont.)
ULLS or SAMS-1 Non-Dedicated Passing Action to DAAS
(Response Code 14)
(Unit-Level Logic)

(O'III ZOVOI ZOGIO)			
Data Element	Record Pos.	Definition/Source	
Fund Code	52-53	a. SARSS-GW enters the value from the fc_ext_* field of the requesting activity's msc_tab if the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not A, B, or C.	
		b. SARSS-GW enters the value from the fc_ext_* field of the requesting activity's msc_tab if the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is A, B, or C and the second position of the matcat field is a number.	
		c. SARSS-GW enters the value GA if the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is A, B, or C and the second position of the matcat field is a letter.	
Distribution Code	54	SARSS-GW enters the value from the distr_cd field of the supporting SSA's abf_xref_tab.	
	55-56	These positions remain blank.	
Project Code, Priority, RDD, and Advice Code	57-66	SARSS-GW perpetuates these values from the source A0	
	67-79	These positions remain blank.	
SARSS-GW Code	80	SARSS-GW enters X.	

Table J-7 (Cont.)
ULLS or SAMS-1 Non-Dedicated Passing Action to DAAS
(Response Code 14)
(Unit-Level Logic)

#### Notes:

- 1. The source A0\_ is the one SARSS-GW received from ULLS, SAMS-1, or DS4.
- 2. The supporting SSA from the dodaac\_tab for the DODAAC in RP 30-35 is determined by the aimi\_tab if the NIIN in RP 12-22 matches an entry and the intermediate support is SARSS, or by the first two positions of the SCMC field of the amdf\_tab for the NIIN in RP 12-22 as follows:
- a. If the NIIN in RP 12-22 matches an entry on the aimi\_tab and the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is not blank, SARSS-GW uses the spt\_ric\_aimi SSA ABF.
- b. If the NIIN in RP 12-22 matches an entry on the aimi\_tab but the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is blank, or the NIIN in RP 12-22 does not match an entry on the aimi\_tab, SARSS-GW uses the first two positions of the scmc field of the amdf\_tab for the NIIN in RP 12-22 to determine the supporting SSA ABF as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting SSA ABF
1 2 3 4 5 6 7 8 9 9	Anything A	spt_ric_i_vi spt_ric_ii_x spt_ric_iii spt_ric_iv spt_ric_v spt_ric_i_vi spt_ric_vii spt_ric_viii spt_ric_ixa spt_ric_ixm spt_ric_ixc
Ö	Anything	spt_ric_ii_x

Table J-7 (Cont.)
ULLS or SAMS-1 Non-Dedicated Passing Action to DAAS
(Response Code 14)
(Unit-Level Logic)

Notes: (Cont.)

- 3. SARSS-GW determines the transaction DODAAC using one of three methods.
- a. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SIC value from the sic field of the abf\_tab as follows:

SIC	DSU Code	Supporting DODAAC
Α	F	ssa_ixa
C F	Α	ssa_ixc
F	K	ssa_iv
J	K	ssa_iii
M	Н	ssa_ixm
Т	K	ssa_vii
U	K	ssa_ii_x

b. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV and the sic field is blank or there is no abf\_tab record, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by converting the value in the scmc field of the amdf\_tab to a SIC value. SARSS-GW then converts the SIC value to a DSU Code as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	SIC	DSU Code	Supporting DODAAC
1 2 3 4 5 6 7 8 9 9	Anything A	UTJFUUTCAMCU	K K K K K K A F H A K	ssa_i_vi ssa_ii_x ssa_iii ssa_iv ssa_v ssa_i_vi ssa_vii ssa_viii ssa_ixa ssa_ixm ssa_ixc ssa_ii_x
	,,g		• •	<u> </u>

Table J-7 (Cont.)
ULLS or SAMS-1 Non-Dedicated Passing Action to DAAS
(Response Code 14)
(Unit-Level Logic)

Notes: (Cont.)

c. If the typ field of the abf\_xref\_tab for the supporting SSA is not DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SCMC value from the amdf\_tab for the stock number in RP 8-22 as follows:

SCMC (2nd pos.)	Supporting DODAAC
Anything	ssa_i_vi
Anything	ssa_ii_x
Anything	ssa_iii
Anything	ssa_iv
Anything	ssa_v
Anything	ssa_i_vi
Anything	ssa_vii
Anything	ssa_viii
Α	ssa_ixa
L	ssa_ixm
Not A or L	ssa_ixc
Anything	ssa_ii_x
	(2nd pos.)  Anything A

Table J-8 DS4 Passing Action to Supporting SARSS2AC/B (DS-Level Logic)				
Data Element	Record Pos.	Definition/Source		
DIC	1-3	SARSS-GW perpetuates this value from the source A0 See Note.		
RIC	4-6	SARSS-GW perpetuates this value from the source A0		
Media and Status Code, NSN, UI, Quantity, DODAAC, Date, SN, Demand Code, Supplementary address, Signal Code, Fund Code, Distribution Code, Priority, RDD, Advice Code, and SARSS-GW Code	7-80	SARSS-GW perpetuates these values from the source A0		
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.		
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from RP 4-6 of the source A0		
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.		
Note: The source A0_ is the one SARSS-GW received from ULLS or SAMS-1.				

Table J-9
DS4, ULLS, or SAMS-1 Passing Action to DAAS (First Denial)
(DS-Level Logic)

(DS-Level Logic)	)	
Data Element	Record Pos.	Definition/Source
DIC	1-3	<ul> <li>a. In CONUS, SARSS-GW perpetuates this value from the source A0 See Note.</li> <li>b. In OCONUS, if the value in the conus_oconus field of the supporting SSA's abf_xref_tab is O, SARSS-GW converts RP 3 as follows:</li> <li>A to 1  B to 2  D to 4  E to 5</li> </ul>
RIC	4-6	SARSS-GW enters the value from the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0
Media and Status Code	7	<ul> <li>a. If RP 45 is Y, SARSS-GW enters the value from media_cd_asl_wh field of the supporting SSA's abf_xref_tab.</li> <li>b. If RP 45 is W, SARSS-GW enters the value from media_cd_nsl_wh field of the supporting SSA's abf_xref_tab.</li> </ul>
NSN	8-22	SARSS-GW perpetuates this value from the source A0
UI, Quantity, DODAAC, Date, and SN	23-43	SARSS-GW perpetuates these values from the AE1 with CB status transaction from DS4.
Demand Code	44	SARSS-GW perpetuates this value from the source A0_ unless it is blank, in which case, SARSS-GW enters R.
Supplementary address	45-50	SARSS-GW perpetuates this value from the AE1 with CB status transaction from DS4.

Table J-9 (Cont.) DS4, ULLS, or SAMS-1 Passing Action to DAAS (First Denial) (DS-Level Logic)				
Data Element	Record Pos.	Definition/Source		
Signal Code	51	a. If RP 51 of the AE1 with CB status transaction from DS4 is J or K, SARSS-GW enters the value from the sig_ded_funded field of the requesting activity's dodaac_tab, or if the sig_ded_funded field is blank, SARSS-GW enters the value from the sig_sa_nsl_stock field of the supporting SSA's abf_xref_tab.		
		b. If RP 51 of the AE1 with CB status transaction from DS4 is A or B, SARSS-GW enters the value from the sig_sa_asl_stock field of the supporting SSA's abf_xref_tab.		
		c. If RP 51 of the AE1 CB with status transaction from DS4 is M, SARSS-GW enters the value from the sig_ded_pa field of the requesting activity's dodaac_tab, or if the sig_ded_pa field is blank, SARSS-GW enters the value from the sig_sa_nsl_pa field of the supporting SSA's abf_xref_tab.		
		d. If RP 51 of the AE1 with CB status transaction from DS4 is D, SARSS-GW enters the value from the sig_sa_asl_pa field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is 2.		
Fund Code	52-53	a. SARSS-GW enters the value from the fc_ext_1 field of the requesting activity's msc_tab if the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not A, B, or C.		
		b. SARSS-GW enters the value from the fc_ext_1 field of the requesting activity's msc_tab if the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is A, B, or C and the second position of the matcat field is 2.		
		c. SARSS-GW enters the value GA if the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is A, B, or C and the second position of the matcat field is not 2.		
Distribution Code	54	SARSS-GW enters the value from the distr_cd field of the supporting SSA's abf_xref_tab.		

T. I. J. (O. 1)					
Table J-9 (Cont.)					
1	DS4, ULLS, or SAMS-1 Passing Action to DAAS (First Denial)				
(DS-Level Logic)					
Data Element	Record	Definition/Source			
	Pos.				
	55-56	These positions remain blank.			
Project Code,	57-66	SARSS-GW perpetuates these values from the source			
Priority, RDD,		A0			
and Advice		· · · ·			
Code					
	67-79	These positions remain blank.			
SARSS-GW	80	SARSS-GW enters X.			
Code					
Note: The source AO is the one CARCC CW/ received from LILL Corr CAMC 4					
Note: The source A0_ is the one SARSS-GW received from ULLS or SAMS-1.					

Table J-10 DS4 Passing Action to DAAS (DS-Level Logic)		
Data Element	Record Pos.	Definition/Source
DIC	1-3	<ul> <li>a. In CONUS, SARSS-GW perpetuates this value from the source A0 See Note 1.</li> <li>b. In OCONUS, if the value in the conus_oconus field of the supporting DSU's abf_xref_tab is O, SARSS-GW converts RP 3 as follows:</li> <li>A to 1  B to 2  D to 4  E to 5</li> </ul>
RIC	4-6	SARSS-GW enters the value from the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0
Media and Status Code	7	<ul> <li>a. If RP 45 is Y, SARSS-GW enters the value from the media_cd_asl_wh field of the supporting SSA's abf_xref_tab. See Note 2.</li> <li>b. If RP 45 is W, SARSS-GW enters the value from the media_cd_nsl_wh field of the supporting SSA's abf_xref_tab.</li> </ul>
NSN, UI, Quantity, DODAAC, Date, SN, Demand Code, and Supplementary address	8-50	SARSS-GW perpetuates these values from the source A0 See Note 3.
Signal Code	51	a. If RP 45 is W, SARSS-GW enters the value from the sig_sa_nsl_stock field of the abf_xref_tab if RP 2 of the matcat field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is 2 or not 2 and the first position of the SOS field of the amdf_tab for that stock number is not A, B, or C.

Table J-10 (Cont.) DS4 Passing Action to DAAS (DS-Level Logic) Data Element Definition/Source Record Pos. b. If RP 45 is W, SARSS-GW enters the value from the Signal Code 51 (Cont.) sig\_sa\_nsl\_pa field of the abf\_xref\_tab if RP 2 of the matcat field of the amdf tab for that stock number is not 2 and the first position of the SOS field of the amdf tab for that stock number is A, B, or C. c. If RP 45 is Y, SARSS-GW enters the value from the sig sa asl stock field of the abf xref tab if RP 2 of the matcat field of the amdf\_tab for that stock number is 2 or not 2 and the first position of the SOS field of the amdf\_tab for that stock number is not A, B, or C. d. If RP 45 is Y. SARSS-GW enters the value from the sig\_sa\_asl\_pa field of the abf\_xref\_tab if RP 2 of the matcat field of the amdf\_tab for that stock number is not 2 and the first position of the SOS field of the amdf tab for that stock number is A, B, or C, SARSS-GW enters the value from the sig nsl stock field of the abf xref tab. Fund Code 52-53 a. SARSS-GW enters the value from the fc\_ext\_\* field of the requesting activity's msc tab if the first position of the SOS field of the amdf tab for the stock number in RP 8-22 of the source A0\_ is not A, B, or C. b. SARSS-GW enters the value from the fc ext \* field of the requesting activity's msc tab if the first position of the SOS field of the amdf tab for the stock number in RP 8-22 of the source A0\_ is A, B, or C and the second position of the matcat field is a number. c. SARSS-GW enters the value GA if the first position of the SOS field of the amdf tab for the stock number in RP 8-22 of the source A0\_ is A, B, or C and the second position of the matcat field is a letter. Distribution 54 SARSS-GW enters the value from the distr\_cd field of the

supporting SSA's abf xref tab.

SARSS-GW perpetuates these values from the source

Code

Project Code,

Priority, RDD,

and Advice Code 55-66

A0\_.

Table J-10 (Cont.)
DS4 Passing Action to DAAS
(DS-Level Logic)

Data Element	Record Pos.	Definition/Source
	67-79	These positions remain blank.
SARSS-GW Code	80	SARSS-GW enters X.

#### Notes:

- 1. The source A0\_ is the one SARSS-GW received from ULLS, SAMS-1, or DS4.
- 2. The supporting SSA from the dodaac\_tab for the DODAAC in RP 30-35 is determined by the aimi\_tab if the NIIN in RP 12-22 matches an entry and the intermediate-level support is SARSS, or by the first two positions of the SCMC field of the amdf\_tab for the NIIN in RP 12-22 as follows:
- a. If the NIIN in RP 12-22 matches an entry on the aimi\_tab and the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is not blank, SARSS-GW uses the spt\_ric\_aimi SSA ABF.
- b. If the NIIN in RP 12-22 matches an entry on the aimi\_tab but the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is blank, or the NIIN in RP 12-22 does not match an entry on the aimi\_tab, SARSS-GW uses the first two positions of the scmc field of the amdf\_tab for the NIIN in RP 12-22 to determine the supporting SSA ABF as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting SSA ABF
1 2 3 4 5 6 7 8 9 9	Anything Anything Anything Anything Anything Anything Anything Anything Anything A L Not A or L Anything	spt_ric_i_vi spt_ric_ii_x spt_ric_iii spt_ric_iv spt_ric_v spt_ric_i_vi spt_ric_vii spt_ric_ixa spt_ric_ixm spt_ric_ixc spt_ric_ixc spt_ric_ii_x

Table J-10 (Cont.) DS4 Passing Action to DAAS (DS-Level Logic)

Notes: (Cont.)

- 3. SARSS-GW determines the transaction DODAAC using one of three methods.
- a. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SIC value from the sic field of the abf\_tab as follows:

SIC	DSU Code	Supporting DODAAC
Α	F	ssa_ixa
С	Α	ssa_ixc
F	K	ssa_iv
J	K	ssa_iii
M	Н	ssa_ixm
Τ	K	ssa_vii
U	K	ssa_ii_x

b. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV and the sic field is blank or there is no abf\_tab record, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by converting the value in the scmc field of the amdf\_tab to a SIC value. SARSS-GW then converts the SIC value to a DSU Code as follows:

1 Anything U K ssa_i_vi	g
2 Anything T K ssa_ii_x 3 Anything J K ssa_iii 4 Anything F K ssa_iv 5 Anything U K ssa_v 6 Anything U K ssa_i_vi 7 Anything T K ssa_vii 8 Anything C A ssa_viii 9 A A F ssa_ixa	
9 L M H ssa_ixm	
9 Not A or L C A ssa_ixc	
0 Anything U K ssa_ii_x	

Table J-10 (Cont.)
DS4 Passing Action to DAAS
(DS-Level Logic)

Notes: (Cont.)

c. If the typ field of the abf\_xref\_tab for the supporting SSA is not DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SCMC value from the amdf\_tab for the stock number in RP 8-22 as follows:

	MC t pos.)	SCMC (2nd pos.)	Supporting DODAAC
1		Anything	ssa_i_vi
2		Anything	ssa_ii_x
3		Anything	ssa_iii
4		Anything	ssa_iv
5		Anything	ssa_v
6		Anything	ssa_i_vi
7		Anything	ssa_vii
8		Anything	ssa_viii
9		Α	ssa_ixa
9		L	ssa_ixm
9		Not A or L	ssa_ixc
0		Anything	ssa_ii_x

Table J-11 Manager Entry Code (MEC) 8 to SAILS (DS4 ASL Replenishment) (Unit-Level Logic)			
Data Element	Record Pos.	Definition/Source	
DIC	1-3	SARSS-GW perpetuates this value from the original A0 See Note 1.	
Manager Code	4-5	a. SARSS-GW enters the value from the mgr_cd field of the supporting SAILS' abf_tab for the stock number in RP 8-22 of the source A0 See Note 2.	
		b. If the mgr_cd field of the supporting SAILS' abf_tab is blank, SARSS-GW enters 0 in RP 4 and enters the first position of the matcat field of the amdf_tab for that stock number in RP 5.	
MEC	6	SARSS-GW enters 8.	
Media and Status Code	7	SARSS-GW enters the value from the media_cd_asl field of the supporting DSU's abf_xref_tab.	
NSN, UI, Quantity, DODAAC, Date, SN, Demand Code, and Supplementary address	8-50	SARSS-GW perpetuates these values from the source A0	
Signal Code	51	a. If the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not A, B, or C, SARSS-GW enters the value from the sig_asl_stock field of the supporting SSA's abf_xref_tab.	
		b. If the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is A, B, or C, SARSS-GW enters the value from the sig_asl_stock field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is 2.	
		c. If the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is A, B, or C, SARSS-GW enters the value from the sig_asl_pa field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is not 2.	

Table J-11 (Cont.)
Manager Entry Code (MEC) 8 to SAILS (DS4 ASL Replenishment)
(Unit-Level Logic)

		<del>-</del>
Data Element	Record Pos.	Definition/Source
	52-53	These positions are blank.
Distribution Code, Project Code, Priority, RDD, and Advice Code	54-66	SARSS-GW perpetuates these values from the source A0
RIC	67-69	SARSS-GW enters the value from the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0
Ownership/ Purpose Code	70	SARSS-GW enters the value from the purpose_cd field of the supporting SAILS' abf_xref_tab.
	71-80	These positions are blank.

### Notes:

- 1. The original A0\_ is the one SARSS-GW received from ULLS or SAMS-1.
- 2. The source A0\_ is the one SARSS-GW created to replenish the DS4 ASL.

Table J-12 Manager Entry Code (MEC) 8 to SAILS (Passing Action to DAAS) (DS- and Unit-Level Logic)		
Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW perpetuates this value from the original A0 See Note 1.
Manager Code	4-5	a. SARSS-GW enters the value from the mgr_cd field of the supporting SAILS' abf_tab for the stock number in RP 8-22 of the source A0 See Note 2.
		b. If the mgr_cd field of the supporting SAILS' abf_tab is blank, SARSS-GW enters a default value 0 in RP 4 and enters the first position of the matcat field of the amdf_tab for the stock number in RP 8-22 of the source A0_ in RP 5.
MEC	6	SARSS-GW enters 8.
Media and Status Code	7	<ul><li>a. SARSS-GW perpetuates this value from the original A0_, unless it is blank.</li><li>b. If it is blank, SARSS-GW enters the value from the</li></ul>
		media_cd_nsl field of the supporting DSU's abf_xref_tab.
NSN, UI, Quantity, DODAAC, Date, SN, Demand Code, and Supplementary address	8-50	SARSS-GW perpetuates these values from the source A0

Data Element Record Pos.  Signal Code 51 a. SARSS-GW perpetuates this value from the original A0_, unless it is blank.
b. If it is blank and RP 2 of the matcat field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is 2 or not 2 and the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not A, B, or C, SARSS-GW enters the value from the sig_nsl_stock field of the abf_xref_tab.  c. If it is blank and RP 2 of the matcat field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not 2 and the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is A, B, or C, SARSS-GW enters the value from the sig_nsl_pa Field of the abf_xref_tab.
Fund Code, Distribution Code, Project Code, Priority, RDD, and Advice Code
RIC SARSS-GW enters the value from the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0
Ownership/ 70 SARSS-GW enters the value from the purpose_cd field of the supporting SAILS' abf_xref_tab.
71-80 These positions remain blank.  General: CreatMEC8 is the SARSS-GW application that creates this transaction.

General: CreatMEC8 is the SARSS-GW application that creates this transaction.

## Notes:

- 1. The original A0\_ is the one SARSS-GW received from DS4, ULLS, or SAMS-1.
- 2. The source A0\_ is the one SARSS-GW uploaded to DAAS.

Table J-13
Manager Entry Code (MEC) 8 to SAILS (Referral Order to a Nonsupporting DS4 or SAILS)

(DS- and Unit-Level Logic)

(BC and office			
Data Element	Record Pos.	Definition/Source	
DIC	1-3	SARSS-GW perpetuates this value from the source A0 See Note 1.	
Manager Code	4-5	<ul><li>a. SARSS-GW enters the value from the mgr_cd field of the supporting SAILS abf_tab for the stock number in RP 8-22 of the source A0</li><li>b. If the mgr_cd field of the supporting SAILS abf_tab is</li></ul>	
		blank, SARSS-GW enters the default 0 in RP 4 and enters the first position of the matcat field of the amdf_tab for that stock number in RP 5.	
MEC	6	SARSS-GW enters 8.	
Media and Status Code	7	<ul> <li>a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.</li> <li>b. If it is blank, SARSS-GW enters the value from the media_cd_nsl field of the supporting DSU's abf_xref_tab.</li> </ul>	
NSN, UI, Quantity, DODAAC, Date, SN, and Demand Code	8-44	SARSS-GW perpetuates these values from the source A0 See Note 2.	
Supplementary address	45-50	<ul> <li>a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.</li> <li>b. If it is blank, SARSS-GW enters the user's prime support DSU DODAAC from the dsu_a, dsu_f, dsu_h, or dsu_k field of the supporting DSU's abf_xref_tab for the stock number in RP 8-22 of the source A0 See Note 3.</li> </ul>	

Table J-13 (Cont.)  Manager Entry Code (MEC) 8 to SAILS (Referral Order to a Nonsupporting DS4 or SAILS)		
(DS- and Unit-Level Logic)		
Data Element	Record Pos.	Definition/Source
Signal Code	51	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.
	b. If it is blank and RP 2 of the matcat field of the amore for the stock number in RP 8-22 of the source A0_ is 2 not 2 and the first position of the SOS field of the amore for that is not A, B, or C, SARSS-GW enters the value the sig_nsl_stock field of the abf_xref_tab.	
for the stock number in RP 8-22 of the source A and the first position of the SOS field of the amount that stock number is A, B, or C, SARSS-GW en		c. If it is blank and RP 2 of the matcat field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not 2 and the first position of the SOS field of the amdf_tab for that stock number is A, B, or C, SARSS-GW enters the value from the sig_nsl_pa field of the abf_xref_tab.
Fund Code, Distribution Code, Project Code, Priority, RDD, and Advice Code	52-66	SARSS-GW perpetuates these values from the source A0
		SARSS-GW enters the SARSS-GW RIC AF4.
		SARSS-GW enters the value from the purpose_cd field of the supporting SAILS' abf_xref_tab.
71-80 These positions remain blank.		

#### Notes:

- 1. The source A0\_ is the one SARSS-GW received from ULLS, SAMS-1, or DS4.
- 2. SARSS-GW determines the transaction DODAAC using one of three methods.
- a. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SIC value from the sic field of the abf\_tab as follows:

SIC	DSU Code	Supporting DODAAC	
A C F	F A K	ssa_ixa ssa_ixc ssa_iv	
J M	K H	ssa_iii ssa_ixm	
T U	K K	ssa_vii ssa ii x	

Table J-13 (Cont.)

Manager Entry Code (MEC) 8 to SAILS (Referral Order to a Nonsupporting DS4 or SAILS) (DS- and Unit-Level Logic)

Notes: (Cont.)

b. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV and the sic field is blank or there is no abf\_tab record, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by converting the value in the scmc field of the amdf\_tab to a SIC value. SARSS-GW then converts the SIC value to a DSU Code as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	SIC	DSU Code	Supporting DODAAC
1	Anything	U	K	ssa_i_vi
2	Anything	Т	K	ssa_ii_x
3	Anything	J	K	ssa_iii
4	Anything	F	K	ssa_iv
5	Anything	U	K	ssa_v
6	Anything	U	K	ssa_i_vi
7	Anything	Т	K	ssa_vii
8	Anything	С	Α	ssa_viii
9	Α	Α	F	ssa_ixa
9	L	M	Н	ssa_ixm
9	Not A or L	С	Α	ssa_ixc
0	Anything	U	K	ssa_ii_x

c. If the typ field of the abf\_xref\_tab for the supporting SSA is not DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SCMC value from the amdf\_tab for the stock number in RP 8-22 as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting DODAAC
1	Anything	ssa_i_vi
2	Anything	ssa_ii_x
3	Anything	ssa_iii
4	Anything	ssa_iv
5	Anything	ssa_v
6	Anything	ssa_i_vi
7	Anything	ssa_vii
8	Anything	ssa_viii
9	Α	ssa_ixa
9	L	ssa_ixm
9	Not A or L	ssa_ixc
0	Anything	ssa ii x

Table J-14 GS Reparable Manager Entry Code (MEC) 8 to SAILS (DS- and Unit-Level Logic)			
Data Element	Record Pos.	Definition/Source	
DIC	1-3	SARSS-GW perpetuates this value from the original A0 See Note 1.	
Manager Code	4-5	a. SARSS-GW enters the value from the mgr_cd field of the supporting SAILS' abf_tab for the stock number in RP 8-22 of the source A0 See Note 2.	
		b. If the mgr_cd field of the supporting SAILS' abf_tab is blank, SARSS-GW enters the default 0 in RP 4 and enters the first position of the matcat field of the amdf_tab for that stock number in RP 5.	
MEC	6	SARSS-GW enters 8.	
Media and Status Code, NSN, UI, Quantity, DODAAC, Date, SN, Demand Code, Supplementary address, Signal Code, Fund Code, Distribution Code, Project Code, Priority, RDD, and Advice Code	7-66	SARSS-GW perpetuates these values from the source A0	
RIC	67-69	SARSS-GW enters the value from the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0	
Ownership/ Purpose Code	70	SARSS-GW enters the value from the purpose_cd field of the supporting SAILS' abf_xref_tab.	
	71-74	These positions remain blank.	
APC	75-78	SARSS-GW enters the value from the gs_repl_apc field of the supporting SAILS' abf_xref_tab.	

Table J-14 (Cont.) GS Reparable Manager Entry Code (MEC) 8 to SAILS (DS- and Unit-Level Logic)			
Data Element Record Definition/Source Pos.		Definition/Source	
79-80 These positions remain blank.		These positions remain blank.	
General: CreatMEC8 is the SARSS-GW application that creates this transaction.			

#### Notes:

- 1. SARSS-GW receives the original A0\_ from DS4, ULLS, or SAMS-1, or creates a DS reparable replenishment requisition that results in replenishment of the GS reparable ASL.
- 2. The source A0\_ is the one SARSS-GW creates to replenish the SAILS GS reparables.

Table J-15 AIMI Replenishment Manager Entry Code (MEC) 8 to SAILS (DS- and Unit-Level Logic)			
Data Element	Record Pos.	Definition/Source	
DIC	1-3	SARSS-GW perpetuates this value from the original A0 See Note 1.	
Manager Code	4-5	a. SARSS-GW enters the value from the mgr_cd field of the supporting SAILS' abf_tab for the stock number in RP 8-22 of the source A0	
		b. If the mgr_cd field of the supporting SAILS' abf_tab is blank, SARSS-GW enters the default 0 in RP 4 and enters the first position of the matcat field of the amdf_tab for that stock number in RP 5.	
MEC	6	SARSS-GW enters 8.	
Media and Status Code, NSN, UI, Quantity, DODAAC, Date, SN, Demand Code, Supplementary address, Signal Code, Fund Code, Distribution Code, Project Code, Priority, RDD, and Advice Code	7-66	SARSS-GW perpetuates these values from the source A0	
RIC 67-69		SARSS-GW enters the value from the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0	
Ownership/ Purpose Code	70	SARSS-GW enters the value from the purpose_cd field of the supporting SAILS' abf_xref_tab.	
	71-74	These positions remain blank.	
APC	75-78	SARSS-GW enters the value from the aimi_repl_apc field of the supporting SAILS' abf_xref_tab.	
	79-80	These positions remain blank.	

Table J-15 (Cont.)

AIMI Replenishment Manager Entry Code (MEC) 8 to SAILS (DS- and Unit-Level Logic)

General: CreatAimiMec8 is the SARSS-GW application that creates this transaction.

#### Notes:

- 1. The original A0\_ is the one SARSS-GW received from ULLS, SAMS-1, or DS4 that generated an AIMI requisition to DAAS.
- 2. The source A0\_ is the one SARSS-GW creates to replenish AIMI.

Table J-16 Manager Entry Code (MEC) 5 to SAILS (GS Reparable Requisition) (DS- and Unit-Level Logic)			
Data Element	Record Pos.	Definition/Source	
DIC	1-3	SARSS-GW perpetuates this value from the original A0 See Note 1.	
Manager Code	4-5	<ul> <li>a. SARSS-GW enters the value from the mgr_cd field of the supporting SAILS' abf_tab for the stock number in RP 8-22 of the source A0 See Note 2.</li> <li>b. If the mgr_cd field of the supporting SAILS' abf_tab is blank, SARSS-GW enters the default 0 in RP 4 and enters the first position of the matcat field of the</li> </ul>	
MEC	6	amdf_tab for that stock number in RP 5.  SARSS-GW enters 5.	
Media and Status Code	7	<ul> <li>a. SARSS-GW perpetuates this value from the original A0_, unless it is blank.</li> <li>b. If it is blank, SARSS-GW enters the value from the media_cd_nsl field of the supporting DSU's abf_xref_tab.</li> </ul>	
NSN, UI, Quantity, DODAAC, Date, SN, and Demand Code	8-44	SARSS-GW perpetuates these values from the source A0	
Supplementary address	45-50	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.	
		b. If it is blank, SARSS-GW enters the user's prime support DSU DODAAC from the dsu_a, dsu_f, dsu_h, or dsu_k field of the supporting DSU's abf_xref_tab for the stock number in RP 8-22 of the source A0 See Note 3.	

Table J-16 (Cont.) Manager Entry Code (MEC) 5 to SAILS (GS Reparable Requisition) (DS- and Unit-Level Logic)			
Data Element	Record Pos.	Definition/Source	
Signal Code	51	<ul> <li>a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.</li> <li>b. If it is blank and RP 2 of the matcat field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is 2 or not 2 and the first position of the SOS field of the amdf_tab for that stock number is not A, B, or C, SARSS-GW enters the value from the sig_nsl_stock field of the abf_xref_tab.</li> <li>c. If it is blank and RP 2 of the matcat field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not 2 and the first position of the SOS field of the amdf_tab for that stock number is A, B, or C, SARSS-GW enters the value from the sig_nsl_pa field of the abf_xref_tab.</li> </ul>	
Fund Code, Distribution Code, Project Code, Priority, RDD, and Advice Code	52-66	SARSS-GW perpetuates these values from the original A0	
	67-69	These positions remain blank.	
Ownership/ Purpose Code	70	SARSS-GW enters the value from the purpose_cd field of the supporting SAILS' abf_xref_tab.	
	71-74	These positions remain blank.	
APC	75-78	SARSS-GW perpetuates this value from the original A0	
79-80 These positions remain blank.		These positions remain blank.	

# General:

- 1. This transaction establishes the due-out record at the supporting SAILS activity.
- 2. CreatReparMec5 is the SARSS-GW application that creates this transaction.

Table J-16 (Cont.)
Manager Entry Code (MEC) 5 to SAILS (GS Reparable Requisition)
(DS- and Unit-Level Logic)

#### Notes:

- 1. The original A0\_ is the ULLS or SAMS-1 A0\_ or the DS reparable requisition that results in SARSS-GW creating a GS reparable requisition for SAILS.
- 2. The source A0\_ is the GS reparable requisition SARSS-GW generates for SAILS.
- 3. SARSS-GW determines the transaction DODAAC using one of three methods.
- a. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SIC value from the sic field of the abf\_tab as follows:

SIC	DSU Code	Supporting DODAAC
A C	F	ssa_ixa
С	Α	ssa_ixc
F	K	ssa_iv
J	K	ssa_iii
M	Н	ssa_ixm
T	K	ssa_vii
U	K	ssa_ii_x

b. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV and the sic field is blank or there is no abf\_tab record, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by converting the value in the scmc field of the amdf\_tab to a SIC value. SARSS-GW then converts the SIC value to a DSU Code as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	SIC	DSU Code	Supporting DODAAC
1	Anything	<u>U</u>	K	ssa_i_vi
2	Anything	I	K	ssa_ii_x
3	Anything	J	K	ssa_iii
4	Anything	F	K	ssa_iv
5	Anything	U	K	ssa_v
6	Anything	U	K	ssa_i_vi
7	Anything	T	K	ssa_vii
8	Anything	С	Α	ssa_viii
9	Α	Α	F	ssa_ixa
9	L	M	Н	ssa_ixm
9	Not A or L	С	Α	ssa_ixc
0	Anything	U	K	ssa_ii_x

Table J-16 (Cont.)

Manager Entry Code (MEC) 5 to SAILS (GS Reparable Requisition)

(DS- and Unit-Level Logic)

Notes: (Cont.)

c. If the typ field of the abf\_xref\_tab for the supporting SSA is not DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SCMC value from the amdf\_tab for the stock number in RP 8-22 as follows:

	SCMC (1st pos.)	SCMC (2nd pos.)	Supporting DODAAC
,	1	Anything	ssa_i_vi
	2	Anything	ssa_ii_x
3	3	Anything	ssa_iii
4	4	Anything	ssa_iv
5	5	Anything	ssa_v
6	6	Anything	ssa_i_vi
7	7	Anything	ssa_vii
8	3	Anything	ssa_viii
Ç	9	Α	ssa_ixa
Ç	9	L	ssa_ixm
ç	9	Not A or L	ssa_ixc
(	)	Anything	ssa_ii_x

Table J-17 AIMI Manager Entry Code (MEC) B to SAILS (DS- and Unit-Level Logic)			
Data Element	Record Pos.	Definition/Source	
DIC	1-3	SARSS-GW perpetuates this value from the source A0 See Note 1.	
Manager Code	4-5	a. SARSS-GW enters the value from the mgr_cd field of the supporting SAILS' abf_tab for the stock number in RP 8-22 of the source A0	
		b. If the mgr_cd field of the supporting SAILS' abf_tab is blank, SARSS-GW enters the default 0 in RP 4 and enters the first position of the matcat field of the amdf_tab for that stock number in RP 5.	
MEC	6	SARSS-GW enters B.	
Media and Status Code	7	<ul> <li>a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.</li> <li>b. If it is blank, SARSS-GW enters the value from the media_cd_nsl field of the supporting DSU's abf_xref_tab.</li> </ul>	
NSN, UI, Quantity, DODAAC, Date, SN, and Demand Code	8-44	SARSS-GW perpetuates these values from the source A0	
Supplementary address	45-50	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.	
		b. If it is blank, SARSS-GW enters the user's prime support DSU's DODAAC address from the dsu_a, dsu_f, dsu_h, or dsu_k field of the supporting DSU's abf_xref_tab for the stock number in RP 8-22 of the source A0 See Note 2.	

Table J-17 (Cont.) AIMI Manager Entry Code (MEC) B to SAILS (DS- and Unit-Level Logic)					
Data Element	ta Element Record Pos. Definition/Source				
Signal Code	51	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.			
		b. If it is blank and RP 2 of the matcat field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is 2 or not 2 and the first position of the SOS field of the amdf_tab for that stock number is not A, B, or C, SARSS-GW enters the value from the sig_nsl_stock field of the abf_xref_tab.			
		c. If it is blank and RP 2 of the matcat field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not 2 and the first position of the SOS field of the amdf_tab for that stock number is A, B, or C, SARSS-GW enters the value from the sig_nsl_pa field of the abf_xref_tab.			
Fund Code, Distribution Code, Project Code, Priority, RDD, and Advice Code	52-66	SARSS-GW perpetuates these values from the source A0			
RIC	67-69	SARSS-GW enters the value from the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0			
Ownership/ Purpose Code	70	SARSS-GW enters the value from the purpose_cd field of the supporting SAILS' abf_xref_tab.			
	71-74	These positions remain blank.			
APC	75-78	SARSS-GW perpetuates this value from the source A0			
	79-80 These positions remain blank.				

Table J-17 (Cont.)
AIMI Manager Entry Code (MEC) B to SAILS
(DS- and Unit-Level Logic)

General: This transaction establishes the due-out record at the supporting SAILS activity.

#### Notes:

- 1. The source A0\_ is the one SARSS-GW received from DS4, ULLS, or SAMS-1 that results in a SARSS-GW-created AIMI requisition.
- 2. SARSS-GW determines the transaction DODAAC using one of three methods.
- a. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SIC value from the sic field of the abf\_tab as follows:

SIC	DSU Code	Supporting DODAAC
Α	F	ssa_ixa
С	Α	ssa_ixc
F	K	ssa_iv
J	K	ssa_iii
M	Н	ssa_ixm
T	K	ssa_vii
U	K	ssa_ii_x

b. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV and the sic field is blank or there is no abf\_tab record, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by converting the value in the scmc field of the amdf\_tab to a SIC value. SARSS-GW then converts the SIC value to a DSU Code as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	SIC	DSU Code	Supporting DODAAC
1 2 3 4 5 6 7 8 9 9	Anything Anything Anything Anything Anything Anything Anything Anything Anything A	UTJFUUTCAMCU	K K K K K A F H A K	ssa_i_vi ssa_ii_x ssa_iii ssa_iv ssa_v ssa_i_vi ssa_vii ssa_viii ssa_ixa ssa_ixm ssa_ixc ssa_ii_x

Table J-17 (Cont.)
AIMI Manager Entry Code (MEC) B to SAILS
(DS- and Unit-Level Logic)

Notes: (Cont.)

c. If the typ field of the abf\_xref\_tab for the supporting SSA is not DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SCMC value from the amdf\_tab for the stock number in RP 8-22 as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting DODAAC
1	Anything	ssa_i_vi
2	Anything	ssa_ii_x
3	Anything	ssa_iii
4	Anything	ssa_iv
5	Anything	ssa_v
6	Anything	ssa_i_vi
7	Anything	ssa_vii
8	Anything	ssa_viii
9	Α	ssa_ixa
9	L	ssa_ixm
9	Not A or L	ssa_ixc
0	Anything	ssa_ii_x

Table J-18 Update Transaction to DS4 (DS4 ASL Requisition to DAAS) (Unit-Level Logic)				
Data Element	Record Pos.	Definition/Source		
DIC, RIC, Media and Status Code, NSN, UI, Quantity, DODAAC, Date, SN, and Demand Code	1-44	SARSS-GW perpetuates these values from the original A0 See Note 1.		
Supplementary address	45-50	SARSS-GW enters the user's prime support DSU DODAAC from the ssa_* field of the supporting DSU's abf_xref_tab for the stock number in RP 8-22 of the original A0 See Note 2.		
Signal Code	51	This position remains blank.		
Fund Code, Distribution Code, Project Code, Priority, RDD, and Advice Code	y,			
DSU Code	67	SARSS-GW enters the DSU Code for the DODAAC in RP 45-50. See Note 3.		
	68-70	These positions remain blank.		
Serial number 71-78 SARSS-GW enters this value from RP 36-43 of source A0		SARSS-GW enters this value from RP 36-43 of the source A0		
Manager Override Code	79	SARSS-GW enters the value from the mgr_ovr_cd field of the supporting DSU's abf_xref_tab.		
Transaction 80 SARSS-GW enters L. Code				

Table J-18 (Cont.)

Update Transaction to DS4 (DS4 ASL Requisition to DAAS)

(Unit-Level Logic)

General: CreatAOL is the SARSS-GW process that creates this transaction in unit-level logic.

#### Notes:

- 1. The original A0\_ is the one SARSS-GW received from ULLS or SAMS-1 that causes SARSS-GW to create an ASL requisition, including a DS reparable, for the user's supporting DS4.
- 2. SARSS-GW determines the transaction DODAAC using one of three methods.
- a. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SIC value from the sic field of the abf\_tab as follows:

SIC	DSU Code	Supporting DODAAC
Α	F	ssa_ixa
С	Α	ssa_ixc
F	K	ssa_iv
J	K	ssa_iii
M	Н	ssa_ixm
T	K	ssa_vii
U	K	ssa_ii_x

b. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV and the sic field is blank or there is no abf\_tab record, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by converting the value in the scmc field of the amdf\_tab to a SIC value. SARSS-GW then converts the SIC value to a DSU Code as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	SIC	DSU Code	Supporting DODAAC
1	Anything	U	K	ssa_i_vi
2	Anything	T	K	ssa_ii_x
3	Anything	J	K	ssa_iii
4	Anything	F	K	ssa_iv
5	Anything	U	K	ssa_v
6	Anything	U	K	ssa_i_vi
7	Anything	Т	K	ssa_vii

Table J-18 (Cont.)
Update Transaction to DS4 (DS4 ASL Requisition to DAAS)
(Unit-Level Logic)

8	Anything	С	А	ssa_viii
Notes: (Cont.)				
SCMC (1st pos.)	SCMC (2nd pos.)	SIC	DSU Code	Supporting DODAAC
9 9 9 0	A L Not A or L Anything	A M C U	F H A K	ssa_ixa ssa_ixm ssa_ixc ssa_ii_x

c. If the typ field of the abf\_xref\_tab for the supporting SSA is not DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SCMC value from the amdf\_tab for the stock number in RP 8-22 as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting DODAAC
1	Anything	ssa_i_vi
2	Anything	ssa_ii_x
3	Anything	ssa_iii
4	Anything	ssa_iv
5	Anything	ssa_v
6	Anything	ssa_i_vi
7	Anything	ssa_vii
8	Anything	ssa_viii
9	Α	ssa_ixa
9	L	ssa_ixm
9	Not A or L	ssa_ixc
0	Anything	ssa_ii_x

3. The source A0\_ is the one SARSS-GW created for the DSU's ASL, including a DS reparable.

Table J-19 Update Transaction to DS4 (DS4 ASL Replenishment to DAAS) (Unit-Level Logic)				
Data Element Record Pos. Definition/Source				
DIC, RIC, Media and Status Code, NSN, UI, Quantity, DODAAC, Date, SN, and Demand Code	1-44	SARSS-GW perpetuates these values from the original A0 See Note 1.		
Supplementary address	45-50	SARSS-GW enters the user's prime support DSU DODAAC from the ssa_* field of the supporting DSU abf_xref_tab for the stock number in RP 8-22 of the original A0 See Note 2.		
Signal Code	51	This position is blank.		
Fund Code, Distribution Code, Project Code, Priority, RDD, and Advice Code	52-66	SARSS-GW perpetuates these values from the original A0		
DSU Code	67	SARSS-GW enters the DSU Code for the DODAAC in RP 45-50. See Note 3.		
	68-70	These positions are blank.		
Serial number 71-78 SARSS-GW enters the value from RP 36-43 source A0		SARSS-GW enters the value from RP 36-43 of the source A0		
Manager Override Code	79	SARSS-GW enters B.		
Transaction 80 SARSS-GW enters L. Code				

Table J-19 (Cont.)
Update Transaction to DS4 (DS4 ASL Replenishment to DAAS)
(Unit-Level Logic)

Notes: (Cont.)

- 1. The original A0\_ is the one SARSS-GW received from ULLS or SAMS-1. The source A0\_ is the A0\_ SARSS-GW passed to DAAS.
- 2. The supporting SSA from the dodaac\_tab for the DODAAC in RP 30-35 is determined by the aimi\_tab if the NIIN in RP 12-22 matches an entry and the intermediate support is SARSS, or by the first two positions of the SCMC field of the amdf\_tab for the NIIN in RP 12-22 as follows:
- a. If the NIIN in RP 12-22 matches an entry on the aimi\_tab and the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is not blank, SARSS-GW uses the spt\_ric\_aimi SSA ABF.
- b. If the NIIN in RP 12-22 matches an entry on the aimi\_tab but the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is blank, or the NIIN in RP 12-22 does not match an entry on the aimi\_tab, SARSS-GW uses the first two positions of the scmc field of the amdf\_tab for the NIIN in RP 12-22 to determine the supporting SSA ABF as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting SSA ABF
1	Anything	spt_ric_i_vi
2	Anything	spt_ric_ii_x
3	Anything	spt_ric_iii
4	Anything	spt_ric_iv
5	Anything	spt_ric_v
6	Anything	spt_ric_i_vi
7	Anything	spt_ric_vii
8	Anything	spt_ric_viii
9	Α	spt_ric_ixa
9	L	spt_ric_ixm
9	Not A or L	spt_ric_ixc
0	Anything	spt_ric_ii_x

Table J-19 (Cont.)
Update Transaction to DS4 (DS4 ASL Replenishment to DAAS)
(Unit-Level Logic)

Notes: (Cont.)

- 3. SARSS-GW determines the transaction DODAAC using one of three methods.
- a. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SIC value from the sic field of the abf\_tab as follows:

SIC	DSU Code	Supporting DODAAC
Α	F	ssa_ixa
С	Α	ssa_ixc
F	K	ssa_iv
J	K	ssa_iii
M	Н	ssa_ixm
Τ	K	ssa_vii
U	K	ssa ii x

b. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV and the sic field is blank or there is no abf\_tab record, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by converting the value in the scmc field of the amdf\_tab to a SIC value. SARSS-GW then converts the SIC value to a DSU Code as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	SIC	DSU Code	Supporting DODAAC
1 2 3 4 5 6 7 8 9 9	Anything Anything Anything Anything Anything Anything Anything Anything Anything A	UTJFUUTCAMCU	K K K K K K A F H A K	ssa_i_vi ssa_ii_x ssa_iii ssa_iv ssa_v ssa_i_vi ssa_vii ssa_viii ssa_ixa ssa_ixm ssa_ixc ssa_ii_x

Table J-19 (Cont.)

Update Transaction to DS4 (DS4 ASL Replenishment to DAAS) (Unit-Level Logic)

Notes: (Cont.)

c. If the typ field of the abf\_xref\_tab for the supporting SSA is not DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SCMC value from the amdf\_tab for the stock number in RP 8-22 as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting DODAAC
1	Anything	ssa_i_vi
2	Anything	ssa_ii_x
3	Anything	ssa_iii
4	Anything	ssa_iv
5	Anything	ssa_v
6	Anything	ssa_i_vi
7	Anything	ssa_vii
8	Anything	ssa_viii
9	Α	ssa_ixa
9	L	ssa_ixm
9	Not A or L	ssa_ixc
0	Anything	ssa_ii_x

Table J-20

Update Transaction to DS4 (Passing Action to DAAS or SAILS, Referral Order to a Nonsupporting DS4 or SAILS, or SAILS Due-Out for GS Reparable and AIMI) (Unit-Level Logic)

Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW perpetuates this value from the source A0 See Note 1.
RIC and Media and Status Code	4-7	These values remain blank.
NSN, UI, Quantity, DODAAC, Date, SN, and Demand Code	8-44	SARSS-GW perpetuates these values from the source A0
Supplementary address	45-50	SARSS-GW enters the user's prime support DSU DODAAC from the ssa_* field of the supporting DSU's abf_xref_tab for the stock number. See Note 2.
Signal Code	51	This value is blank.
Fund Code, Distribution Code, Project Code, Priority, RDD, and Advice Code	52-66	SARSS-GW perpetuates these values from the source A0
DSU Code	67	SARSS-GW enters the DSU Code for the entry in RP 45-50. See Note 3.
	68-78	These positions are blank.
Manager Override Code	79	SARSS-GW enters B.
Transaction Code	80	SARSS-GW enters L.

Table J-20 (Cont.)

Update Transaction to DS4 (Passing Action to DAAS or SAILS, Referral Order to a Nonsupporting DS4 or SAILS, or SAILS Due-Out for GS Reparable and AIMI) (Unit-Level Logic)

#### Notes:

- 1. The source A0\_ is the one SARSS-GW received from ULLS or SAMS-1 and uploaded to DAAS or downloaded to SAILS, generated a referral order to a non-supporting DS4 or SAILS, or created a due-out from SAILS for a GS reparable or AIMI.
- 2. The supporting SSA from the dodaac\_tab for the DODAAC in RP 30-35 is determined by the aimi\_tab if the NIIN in RP 12-22 matches an entry and the intermediate support is SARSS, or by the first two positions of the SCMC field of the amdf\_tab for the NIIN in RP 12-22 as follows:
- a. If the NIIN in RP 12-22 matches an entry on the aimi\_tab and the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is other than blank, SARSS-GW uses the spt\_ric\_aimi SSA ABF.
- b. If the NIIN in RP 12-22 matches an entry on the aimi\_tab but the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is blank, or the NIIN in RP 12-22 does not match an entry on the aimi\_tab, SARSS-GW uses the first two positions of the scmc field of the amdf\_tab for the NIIN in RP 12-22 to determine the supporting SSA ABF as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting SSA ABF
1 2 3 4 5 6 7 8 9	Anything Anything Anything Anything Anything Anything Anything Anything Anything A	spt_ric_i_vi spt_ric_ii_x spt_ric_iii spt_ric_iv spt_ric_v spt_ric_i_vi spt_ric_vii spt_ric_viii spt_ric_ixa
9	Not A or L	spt_ric_ixm spt_ric_ixc
0	Anything	spt_ric_ii_x

Table J-20 (Cont.)

Update Transaction to DS4 (Passing Action to DAAS or SAILS, Referral Order to a Nonsupporting DS4 or SAILS, or SAILS Due-Out for GS Reparable and AIMI) (Unit-Level Logic)

Notes: (Cont.)

- 3. SARSS-GW determines the transaction DODAAC using one of three methods.
- a. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SIC value from the sic field of the abf\_tab as follows:

SIC	DSU Code	Supporting DODAAC
Α	F	ssa_ixa
С	Α	ssa_ixc
F	K	ssa_iv
J	K	ssa_iii
M	Н	ssa_ixm
T	K	ssa_vii
U	K	ssa_ii_x

b. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV and the sic field is blank or there is no abf\_tab record, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by converting the value in the scmc field of the amdf\_tab to a SIC value. SARSS-GW then converts the SIC value to a DSU Code as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	SIC	DSU Code	Supporting DODAAC
1	Anything	U	K	ssa_i_vi
2	Anything	T	K	ssa_ii_x
3	Anything	J	K	ssa_iii
4	Anything	F	K	ssa_iv
5	Anything	U	K	ssa_v
6	Anything	U	K	ssa_i_vi
7	Anything	T	K	ssa_vii
8	Anything	С	Α	ssa_viii
9	Α	Α	F	ssa_ixa
9	L	M	Н	ssa_ixm
9	Not A or L	С	Α	ssa_ixc
0	Anything	U	K	ssa_ii_x

Table J-20 (Cont.)

Update Transaction to DS4 (Passing Action to DAAS or SAILS, Referral Order to a Nonsupporting DS4 or SAILS, or SAILS Due-Out for GS Reparable and AIMI) (Unit-Level Logic)

Notes: (Cont.)

c. If the typ field of the abf\_xref\_tab for the supporting SSA is not DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SCMC value from the amdf\_tab for the stock number in RP 8-22 as follows:

	MC t pos.)	SCMC (2nd pos.)	Supporting DODAAC
1		Anything	ssa_i_vi
2		Anything	ssa_ii_x
3		Anything	ssa_iii
4		Anything	ssa_iv
5		Anything	ssa_v
6		Anything	ssa_i_vi
7		Anything	ssa_vii
8		Anything	ssa_viii
9		Α	ssa_ixa
9		L	ssa_ixm
9		Not A or L	ssa_ixc
0		Anything	ssa_ii_x

# Table J-21

A4\_ Dedicated Referral Order to a DS4 or SAILS

(Response Code 11, 23, or 45)

(DS- and Unit-Level Logic)

Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW enters A4 in RP 1-2 and perpetuates the value in RP 3 from the source A0 See Note 1.
RIC	4-6	SARSS-GW enters the value from the ric field of the shipping activity's abf_xref_tab.
Media and Status Code	7	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.
		b. If it is blank, SARSS-GW enters the value from the media_cd_nsl field of the supporting SSA's abf_xref_tab.
FSC	8-11	SARSS-GW perpetuates this value from the source A0_ if it matches the amdf_tab. If it does not match, SARSS-GW applies the correct FSC from the amdf_tab.
NIIN and UI	12-24	SARSS-GW perpetuates these values from the source A0
Quantity	25-29	a. SARSS-GW perpetuates this value from the source A0_ for Response Codes 11 and 23.
		b. SARSS-GW enters the quantity found for Response Code 45.
DODAAC, Date, and SN	30-43	SARSS-GW perpetuates these values from the source A0
Suffix Code	44	SARSS-GW enters A.
Supplementary address	45-50	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.
		b. If it is blank, SARSS-GW enters the user's support SSA DODAAC for the NSN. See Note 2.

Table J-21 (Cont.)			
A4_ Dedicated Referral Order to a DS4 or SAILS (Response Code 11, 23, or 45) (DS- and Unit-Level Logic)			
Data Element	Record Pos.	Definition/Source	
Signal Code	51	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.	
		b. If it is blank and the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not A, B, or C, SARSS-GW enters the value from the sig_ded_funded field of the requesting activity's dodaac_tab, or if the sig_ded_funded field is blank, SARSS-GW enters the value from the sig_nsl_stock field of the supporting SSA's abf_xref_tab. See Note 3.	
		c. If it is blank and the first position of the SOS field of the amdf_tab for that stock number is A, B, or C, SARSS-GW enters the value from the sig_ded_funded field of the requesting activity's dodaac_tab if the second position of the matcat field of the amdf_tab is 2, or if the sig_ded_funded field is blank, SARSS-GW enters the value from the sig_nsl_stock field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is 2.	
		d. If it is blank and the first position of the SOS field of the amdf_tab for that stock number is A, B, or C, SARSS-GW enters the value from the sig_ded_pa field of the requesting activity's dodaac_tab if the second position of the matcat field of the amdf_tab is not 2, or if the sig_ded_funded field is blank, SARSS-GW enters the value from the sig_nsl_pa field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is not 2.	
Fund Code	52-53	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.	
		b. If it is blank and RP 51 is A or J, SARSS-GW enters the value from the fc_inter_1 field of the msc_tab for the DODAAC in RP 30-35.	
		c. If it is blank and RP 51 is B or K, SARSS-GW enters	

DODAAC in RP 45-50.

the value from the fc\_inter\_1 field of the msc\_tab for the

Table J-21 (Cont.)

A4\_ Dedicated Referral Order to a DS4 or SAILS

(Response Code 11, 23, or 45)

(DS- and Unit-Level Logic)

Data Element	Record Pos.	Definition/Source
Distribution Code, Project Code, Priority, RDD, and Advice Code	54-66	SARSS-GW perpetuates these values from the source A0
	67-70	These positions are blank.
Condition Code	71	SARSS-GW enters A.
	72-73	These positions are blank.
SARSS-GW RIC	74-76	SARSS-GW enters AF4.
	77-80	These positions are blank.

General: SARSS-GW generates this referral order to satisfy an A0\_ it received from a DS4, ULLS, or SAMS-1 supported by SAILS or by SARSS when the A0\_ meets the dedicated rule.

#### Notes:

- 1. The source A0\_ refers to the one SARSS-GW received from DS4, ULLS, or SAMS-1.
- 2. SARSS-GW determines the transaction DODAAC using one of three methods.
- a. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SIC value from the sic field of the abf\_tab as follows:

SIC	DSU Code	Supporting DODAAC
A C F J M	F A K K H	ssa_ixa ssa_ixc ssa_iv ssa_iii ssa_ixm ssa_vii
Ü	K	ssa_vii ssa_ii_x

Table J-21 (Cont.)
A4\_ Dedicated Referral Order to a DS4 or SAILS
(Response Code 11, 23, or 45)
(DS- and Unit-Level Logic)

Table J-21 (Cont.)
A4\_ Dedicated Referral Order to a DS4 or SAILS
(Response Code 11, 23, or 45)
(DS- and Unit-Level Logic)

Notes: (Cont.)

b. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV and the sic field is blank or there is no abf\_tab record, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by converting the value in the scmc field of the amdf\_tab to a SIC value. SARSS-GW then converts the SIC value to a DSU Code as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	SIC	DSU Code	Supporting DODAAC
1	Anything	U	K	ssa_i_vi
2	Anything	T	K	ssa_ii_x
3	Anything	J	K	ssa_iii
4 5	Anything Anything Anything	F U	K K	ssa_ii ssa_iv ssa_v
6	Anything	U	K	ssa_i_vi
7	Anything	T	K	ssa_vii
8	Anything	C	A	ssa_viii
9	A	A	F	ssa_ixa
9	L	M	H	ssa_ixm
9	Not A or L	C	A	ssa_ixc
0	Anything	U	K	ssa_ii_x

c. If the typ field of the abf\_xref\_tab for the supporting SSA is not DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SCMC value from the amdf\_tab for the stock number in RP 8-22 as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting DODAAC
1	Anything	ssa_i_vi
2	Anything	ssa_ii_x
3	Anything	ssa_iii
4	Anything	ssa_iv
5	Anything	ssa_v
6	Anything	ssa_i_vi
7	Anything	ssa_vii
8	Anything	ssa_viii
9	Α	ssa_ixa
9	L	ssa_ixm
9	Not A or L	ssa_ixc
0	Anything	ssa_ii_x

Table J-21 (Cont.)
A4\_ Dedicated Referral Order to a DS4 or SAILS
(Response Code 11, 23, or 45)
(DS- and Unit-Level Logic)

Notes: (Cont.)

- 3. The supporting SSA from the dodaac\_tab for the DODAAC in RP 30-35 is determined by the aimi\_tab if the NIIN in RP 12-22 matches an entry and the intermediate support is SARSS, or by the first two positions of the SCMC field of the amdf\_tab for the NIIN in RP 12-22 as follows:
- a. If the NIIN in RP 12-22 matches an entry on the aimi\_tab and the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is not blank, SARSS-GW uses the spt\_ric\_aimi SSA ABF.
- b. If the NIIN in RP 12-22 matches an entry on the aimi\_tab but the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is blank, or the NIIN in RP 12-22 does not match an entry on the aimi\_tab, SARSS-GW uses the first two positions of the scmc field of the amdf\_tab for the NIIN in RP 12-22 to determine the supporting SSA ABF as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting SSA ABF
1 2 3 4 5 6 7 8 9 9	Anything A	spt_ric_i_vi spt_ric_ii_x spt_ric_iii spt_ric_iv spt_ric_v spt_ric_vii spt_ric_viii spt_ric_ixa spt_ric_ixm spt_ric_ixc spt_ric_ii_x
	, ,	. – – –

Table J-22
A4\_ Non-Dedicated Referral Order to a DS4 or SAILS
(Response Code 11 or 23)
(Unit-Level Logic)

` ,		
Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW enters 4A in RP 1-2 and perpetuates the value in RP 3 from the source A0 See Note 1.
RIC	4-6	SARSS-GW enters the value from the ric field of the shipping activity's abf_xref_tab.
Media and Status Code	7	SARSS-GW enters the value from the media_cd_asl field of the supporting SSA's abf_xref_tab. See Note 2.
FSC	8-11	SARSS-GW perpetuates this value from the source A0_ if it matches the amdf_tab. If it does not match, SARSS-GW applies the correct FSC from the amdf_tab.
NIIN, UI, and Quantity	12-29	SARSS-GW perpetuates these values from the source A0
DODAAC	30-35	SARSS-GW enters the user's prime support SSA DODAAC.
Date	36-39	SARSS-GW enters the date as YDDD.
Serial number	40-43	SARSS-GW uses the docreg field of the supporting SSA's dodaac_tab to determine the serial number to enter as follows:
		RP 40 is X, V, or Z. RP 41-43 is the next available sequence number, beginning with 001 each day.
Supplementary address	45-50	SARSS-GW enters the prime support DODAAC. If the DODAAC in RP 30-35 represents an SSA, SARSS-GW leaves this field blank. See Note 3.

Table J-22 (Cont.)
A4\_ Non-Dedicated Referral Order to a DS4 or SAILS (Response Code 11 or 23)
(Unit-Level Logic)

(Offic-Level Logic)	'	
Data Element	Record Pos.	Definition/Source
Signal Code	51	<ul> <li>a. If the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source AO_ is not A, B, or C, SARSS-GW enters the value from the sig_asl_stock field of the supporting SSA's abf_xref_tab.</li> <li>b. If the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source AO_ is A, B, or C, SARSS-GW enters the value from the sig_asl_stock field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is 2.</li> <li>c. If the first position of the SOS field of the amdf_tab for that stock number is A, B, or C, SARSS-GW enters the value from the sig_asl_pa field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is not 2.</li> </ul>
Fund Code	52-53	<ul> <li>a. If the msc fields of the dodaac_tabs for the DODAACs in RP 30-35 of the source A0_ and RP 30-35 of this A4_ are the same, SARSS-GW perpetuates this value from the source A0_, unless it is blank.</li> <li>b. If this field is blank and the msc fields of the dodaac_tabs for the DODAACs in RP 30-35 of the source A0_ and RP 30-35 of this A4_ are the same, SARSS-GW enters the value from the fc_inter_1 field of the msc_tab for the DODAAC in RP 30-35 of the source A0</li> <li>c. If this field is blank and the msc fields of the dodaac_tabs for the DODAACs in RP 30-35 of the source A0_ and RP 30-35 of this A4_ are not the same, SARSS-GW enters the value from the fc_inter_1 field of the msc_tab for the DODAAC in RP 30-35 of this A4</li> </ul>
Distribution Code, Project Code, Priority, RDD, and Advice Code	54-66	SARSS-GW perpetuates these values from the source A0
	67-70	These positions are blank.
Condition Code	71	SARSS-GW enters A.

Table J-22 (Cont.)
A4\_ Non-Dedicated Referral Order to a DS4 or SAILS
(Response Code 11 or 23)
(Unit-Level Logic)

Data Element	Record Pos.	Definition/Source
	72-73	These positions are blank.
SARSS-GW RIC	74-76	SARSS-GW enters AF4.
	77-80	These positions are blank.

General: This referral order is generated to satisfy an A0\_ SARSS-GW received from an ULLS or SAMS-1 that is supported by SARSS and that meets the non-dedicated rule.

#### Notes:

- 1. The source A0\_ refers to the A0\_ that was received by SARSS-GW from DS4, ULLS, or SAMS-1.
- 2. The supporting SSA from the dodaac\_tab for the DODAAC in RP 30-35 is determined by the aimi\_tab if the NIIN in RP 12-22 matches an entry and the intermediate support is SARSS, or by the first two positions of the SCMC field of the amdf\_tab for the NIIN in RP 12-22 as follows:
- a. If the NIIN in RP 12-22 matches an entry on the aimi\_tab and the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is not blank, SARSS-GW uses the spt\_ric\_aimi SSA ABF.
- b. If the NIIN in RP 12-22 matches an entry on the aimi\_tab but the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is blank, or the NIIN in RP 12-22 does not match an entry on the aimi\_tab, SARSS-GW uses the first two positions of the scmc field of the amdf tab for the NIIN in RP 12-22 to determine the supporting SSA ABF as follows:

	CMC st pos.)	SCMC (2nd pos.)	Supporting SSA ABF
1 2 3 4 5 6 7 8 9 9		Anything A	spt_ric_i_vi spt_ric_ii_x spt_ric_iii spt_ric_iv spt_ric_v spt_ric_i_vi spt_ric_vii spt_ric_viii spt_ric_ixa spt_ric_ixm spt_ric_ixc spt_ric_ixc spt_ric_ii_x
•		,	-1-1-1-1

Table J-22 (Cont.)
A4\_ Non-Dedicated Referral Order to a DS4 or SAILS
(Response Code 11 or 23)
(Unit-Level Logic)

Notes: (Cont.)

- 3. SARSS-GW determines the transaction DODAAC using one of three methods.
- a. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SIC value from the sic field of the abf\_tab as follows:

SIC	DSU Code	Supporting DODAAC
Α	F	ssa_ixa
С	Α	ssa_ixc
F	K	ssa_iv
J	K	ssa_iii
M	Н	ssa_ixm
Τ	K	ssa_vii
U	K	ssa_ii_x

b. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV and the sic field is blank or there is no abf\_tab record, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by converting the value in the scmc field of the amdf\_tab to a SIC value. SARSS-GW then converts the SIC value to a DSU Code as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	SIC	DSU Code	Supporting DODAAC
1 2 3 4 5 6 7 8 9	Anything A	U T J F U U T C A M C	K K K K K K A F H A	ssa_i_vi ssa_ii_x ssa_iii ssa_iv ssa_v ssa_i_vi ssa_vii ssa_viii ssa_ixa ssa_ixm ssa_ixc
0	Anything	U	K	ssa_ii_x

Table J-22 (Cont.)
A4\_ Non-Dedicated Referral Order to a DS4 or SAILS
(Response Code 11 or 23)
(Unit-Level Logic)

Notes: (Cont.)

c. If the typ field of the abf\_xref\_tab for the supporting SSA is not DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SCMC value from the amdf\_tab for the stock number in RP 8-22 as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting DODAAC
1	Anything	ssa_i_vi
2	Anything	ssa_ii_x
3	Anything	ssa_iii
4	Anything	ssa_iv
5	Anything	ssa_v
6	Anything	ssa_i_vi
7	Anything	ssa_vii
8	Anything	ssa_viii
9	Α	ssa_ixa
9	L	ssa_ixm
9	Not A or L	ssa_ixc
0	Anything	ssa_ii_x

Table J-23

A4\_ Dedicated Referral Order to a SARSS1

(Response Code 23)

(DS- and Unit-Level Logic)

,	• ,	
Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW enters A4 in RP 1-2 and perpetuates the value in RP 3 from the source A0 See Note 1.
RIC	4-6	SARSS-GW enters the value from the ric field of the shipping activity's abf_xref_tab.
Media and Status Code	7	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.
		b. If it is blank, SARSS-GW enters the value from the media_cd_nsl field of the supporting SSA's abf_xref_tab . See Note 2.
FSC	8-11	SARSS-GW perpetuates this value from the source A0_ if it matches the amdf_tab. If it does not match, SARSS-GW applies the correct FSC from the amdf_tab.
NIIN	12-22	SARSS-GW enters the value of the NIIN that was found for referral, unless the A0_ states do not substitute, in which case it enters the value of the source A0
	23-29	SARSS-GW perpetuates this value from the source A0
Document number	30-43	SARSS-GW perpetuates this value from the source A0
Suffix Code	44	SARSS-GW enters A.
Supplementary address	45-50	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.
		b. If it is blank, SARSS-GW enters the user's prime support SSA DODAAC. See Note 2.

Table J-23 (Cont.)
A4\_ Dedicated Referral Order to a SARSS1
(Response Code 23)
(DS- and Unit-Level Logic)

(DS- and Unit-Lev	(DS- and Unit-Level Logic)		
Data Element	Record Pos.	Definition/Source	
Signal Code	51	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.  b. If it is blank and the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not A, B, or C, SARSS-GW enters the value from the sig_ded_funded field of the requesting activity's dodaac_tab, or if the sig_ded_funded field is blank, SARSS-GW enters the value from the sig_nsl_stock field of the supporting SSA's abf_xref_tab.  c. If it is blank and the first position of the SOS field of the amdf_tab for that stock number is A, B, or C, SARSS-GW enters the value from the sig_ded_funded field of the requesting activity's dodaac_tab, or if the second position of the matcat field of the amdf_tab is 2, or if the sig_ded_funded field is blank, SARSS-GW enters the value from the sig_nsl_stock field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is 2.  d. If it is blank and the first position of the SOS field of the amdf_tab for that stock number is A, B, or C, SARSS-GW enters the value from the sig_ded_pa field of the requesting activity's dodaac_tab if the second position of the matcat field of the amdf_tab is not 2, or if the sig_ded_funded field is blank, SARSS-GW enters the value from the sig_nsl_pa field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is not 2.	
Fund Code	52-53	<ul> <li>a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.</li> <li>b. If it is blank, SARSS GW enters the value from the fc_inter_1 field of the msc_tab for the DODAAC in RP 30-35.</li> </ul>	
	54-56	SARSS-GW perpetuates these values from the source A0	

Table J-23 (Cont.)
A4\_ Dedicated Referral Order to a SARSS1

(Response Code 23)

(DS- and Unit-Level Logic)

(Do and only Lot	(DO and One Level Logic)			
Data Element	Record Pos.	Definition/Source		
Project Code	57-59	SARSS-GW enters the Project Code from the abf_tab where the NIIN/qty was found.		
	60-66	SARSS-GW perpetuates this value from the source A0		
Date Rqn received	67-69	This field contains the date the requisition was received from the SARSS-GW (Julian date).		
Ownership/ Purpose Code	70	SARSS-GW enters the OPC from the abf_tab record where the NIIN/qty was found.		
Condition Code	71	SARSS-GW enters the Condition Code from the abf_tab record where the quantity was found.		
Issue indicator	72	SARSS-GW enters a constant 1 for any quantity found above the RO. See Note 3.		
Filler	73	This position is blank.		
SARSS-GW RIC	74-76	SARSS-GW enters AF4.		
Filler	77-80	These positions are blank.		
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.		
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from the RIC field of the abf_xref_tab for the activity where the quantity was found.		
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.		

Table J-23 (Cont.)
A4\_ Dedicated Referral Order to a SARSS1 (Response Code 23)
(DS- and Unit-Level Logic)

#### Notes:

- 1. The source A0\_ is the one SARSS-GW received from ULLS, SAMS-1, or DS4.
- 2. The supporting SSA from the dodaac\_tab for the DODAAC in RP 30-35 is determined. The NIIN in RP 12-22 determines what SSA's abf\_xref\_tab is used, based on the SCMC from the amdf\_tab. All Media and Status Codes, Signal Codes, RICs, and supporting DODAACs will be taken from this table.

SCMC (2nd pos.)	Supporting SSA ABF
Anything	spt_ric_i_vi
Anything	spt_ric_ii_x
Anything	spt_ric_iii
Anything	spt_ric_iv
Anything	spt_ric_v
Anything	spt_ric_vi
Anything	spt_ric_vii
Anything	spt_ric_viii
Α	spt_ric_ixa
L	spt_ric_ixm
Not A or L	spt_ric_ixc
Anything	spt_ric_x
	(2nd pos.)  Anything A

- 3. The SARSS-GW determines the issue\_ind code by the item not being ISM. The code is always 1 for non-ISM items. Issue to the requisitioning objective (RO).
- 4. The SARSS-GW generates this referral order for a SARSS1 supported by another SARSS2AC/B to satisfy an A0\_ received from SARSS2AC/B for a NIIN group that is above the RO in the corps.

Table J-24
A4\_ Non-Dedicated Referral Order to a SARSS1
(Response Code 23)
(Unit-Level Logic)

Data Element         Record Pos.         Definition/Source           DIC         1-3         SARSS-GW enters A4 in RP 1-2 and perpetuates the value in RP 3 from the source A0 See Note 1.           RIC         4-6         SARSS-GW enters the value from the ric field of the shipping activity's abf_xref_tab.           Media and Status Code         7         a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.           b. If it is blank, SARSS-GW enters the value of the media_cd_asl field from the supporting SSA's abf_xref_tab. See Note 2.           FSC         8-11         SARSS-GW perpetuates this value from the source A0_ if it matches the amdf_tab. If it does not match, SARSS-GW applies the correct FSC from the amdf_tab.           NIIN         12-22         SARSS-GW enters the value of the NIIN that was found for referral, unless the A0_ states do not substitute, in which case it enters the value of the source A0           DODAAC         30-35         SARSS-GW perpetuates this value from the source A0           DODAAC         30-35         SARSS-GW enters the user's prime support SSA DODAAC for that class of supply. See Note 2.           DOC-DATE         36-39         SARSS-GW enters the current Julian date as YDDD.           Serial number         40-43         SARSS-GW uses the docreg field of the supporting SSA's dodaac_tab to determine what serial number to enter as follows:	(Ornit Edvar Edgie)	(OTHE EGVEL EGGIO)			
value in RP 3 from the source A0 See Note 1.  RIC	Data Element		Definition/Source		
Shipping activity's abf_xref_tab.  Media and Status Code  7 a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.  b. If it is blank, SARSS-GW enters the value of the media_cd_asl field from the supporting SSA's abf_xref_tab. See Note 2.  FSC  8-11 SARSS-GW perpetuates this value from the source A0_ if it matches the amdf_tab. If it does not match, SARSS-GW applies the correct FSC from the amdf_tab.  NIIN  12-22 SARSS-GW enters the value of the NIIN that was found for referral, unless the A0_ states do not substitute, in which case it enters the value of the source A0  23-29 SARSS-GW perpetuates this value from the source A0  DODAAC  30-35 SARSS-GW enters the user's prime support SSA DODAAC for that class of supply. See Note 2.  DOC-DATE  36-39 SARSS-GW enters the current Julian date as YDDD.  Serial number  40-43 SARSS-GW uses the docreg field of the supporting SSA's dodaac_tab to determine what serial number to enter as follows:  RP 40 is X, V, or Z.  RP 41-43 is the next available sequence number, beginning with 001 each day.	DIC	1-3			
Status Code  A0_, unless it is blank.  b. If it is blank, SARSS-GW enters the value of the media_cd_asl field from the supporting SSA's abf_xref_tab. See Note 2.  FSC  8-11  SARSS-GW perpetuates this value from the source A0_ if it matches the amdf_tab. If it does not match, SARSS-GW applies the correct FSC from the amdf_tab.  NIIN  12-22  SARSS-GW enters the value of the NIIN that was found for referral, unless the A0_ states do not substitute, in which case it enters the value of the source A0  23-29  SARSS-GW perpetuates this value from the source A0  DODAAC  30-35  SARSS-GW enters the user's prime support SSA DODAAC for that class of supply. See Note 2.  DOC-DATE  36-39  SARSS-GW enters the current Julian date as YDDD.  Serial number  40-43  SARSS-GW uses the docreg field of the supporting SSA's dodaac_tab to determine what serial number to enter as follows:  RP 40 is X, V, or Z.  RP 41-43 is the next available sequence number, beginning with 001 each day.	RIC	4-6			
media_cd_asl field from the supporting SSA's abf_xref_tab. See Note 2.  FSC  8-11  SARSS-GW perpetuates this value from the source AO_ if it matches the amdf_tab. If it does not match, SARSS-GW applies the correct FSC from the amdf_tab.  NIIN  12-22  SARSS-GW enters the value of the NIIN that was found for referral, unless the AO_ states do not substitute, in which case it enters the value of the source AO  23-29  SARSS-GW perpetuates this value from the source AO  DODAAC  30-35  SARSS-GW enters the user's prime support SSA DODAAC for that class of supply. See Note 2.  DOC-DATE  36-39  SARSS-GW enters the current Julian date as YDDD.  Serial number  40-43  SARSS-GW uses the docreg field of the supporting SSA's dodaac_tab to determine what serial number to enter as follows:  RP 40 is X, V, or Z.  RP 41-43 is the next available sequence number, beginning with 001 each day.		7	· ·		
A0_ if it matches the amdf_tab. If it does not match, SARSS-GW applies the correct FSC from the amdf_tab.  NIIN  12-22  SARSS-GW enters the value of the NIIN that was found for referral, unless the A0_ states do not substitute, in which case it enters the value of the source A0  23-29  SARSS-GW perpetuates this value from the source A0  DODAAC  30-35  SARSS-GW enters the user's prime support SSA DODAAC for that class of supply. See Note 2.  DOC-DATE  36-39  SARSS-GW enters the current Julian date as YDDD.  Serial number  40-43  SARSS-GW uses the docreg field of the supporting SSA's dodaac_tab to determine what serial number to enter as follows:  RP 40 is X, V, or Z.  RP 41-43 is the next available sequence number, beginning with 001 each day.			media_cd_asl field from the supporting SSA's		
found for referral, unless the A0_ states do not substitute, in which case it enters the value of the source A0  23-29 SARSS-GW perpetuates this value from the source A0  DODAAC 30-35 SARSS-GW enters the user's prime support SSA DODAAC for that class of supply. See Note 2.  DOC-DATE 36-39 SARSS-GW enters the current Julian date as YDDD.  Serial number 40-43 SARSS-GW uses the docreg field of the supporting SSA's dodaac_tab to determine what serial number to enter as follows:  RP 40 is X, V, or Z.  RP 41-43 is the next available sequence number, beginning with 001 each day.	FSC	8-11	A0_ if it matches the amdf_tab. If it does not match, SARSS-GW applies the correct FSC from the		
DODAAC  30-35  SARSS-GW enters the user's prime support SSA DODAAC for that class of supply. See Note 2.  DOC-DATE  36-39  SARSS-GW enters the current Julian date as YDDD.  Serial number  40-43  SARSS-GW uses the docreg field of the supporting SSA's dodaac_tab to determine what serial number to enter as follows:  RP 40 is X, V, or Z.  RP 41-43 is the next available sequence number, beginning with 001 each day.	NIIN	12-22	found for referral, unless the A0_ states do not substitute, in which case it enters the value of the		
DOC-DATE  36-39  SARSS-GW enters the current Julian date as YDDD.  Serial number  40-43  SARSS-GW uses the docreg field of the supporting SSA's dodaac_tab to determine what serial number to enter as follows:  RP 40 is X, V, or Z.  RP 41-43 is the next available sequence number, beginning with 001 each day.		23-29	· ·		
Serial number  40-43  SARSS-GW uses the docreg field of the supporting SSA's dodaac_tab to determine what serial number to enter as follows:  RP 40 is X, V, or Z.  RP 41-43 is the next available sequence number, beginning with 001 each day.	DODAAC	30-35	·		
SSA's dodaac_tab to determine what serial number to enter as follows:  RP 40 is X, V, or Z.  RP 41-43 is the next available sequence number, beginning with 001 each day.	DOC-DATE	36-39	SARSS-GW enters the current Julian date as YDDD.		
RP 41-43 is the next available sequence number, beginning with 001 each day.	Serial number	40-43	SSA's dodaac_tab to determine what serial number to		
beginning with 001 each day.			RP 40 is X, V, or Z.		
Suffix Code 44 SARSS-GW enters A.			·		
	Suffix Code	44	SARSS-GW enters A.		

Table J-24 (Cont.)			
A4_ Non-Dedicated Referral Order to a SARSS1 (Response Code 23) (Unit-Level Logic)			
Data Element	Record Pos.	Definition/Source	
Supplementary	45-50	a. SARSS-GW enters Y in RP 45.	
address		b. SARSS-GW enters Y in RP 46 if the SLC on the supporting ABF for the stock number in RP 8-22 is not Z. If it is Z, SARSS-GW enters W.	
		c. SARSS-GW enters W in RP 47.	
		d. Positions 48-49 are blank.	
Signal Code	51	a. If this field is blank and the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not A, B, or C, SARSS-GW enters the value from the sig_asl_stock field of the supporting SSA's abf_xref_tab. See Note 2.	
		b. If the first position of the SOS field of the amdf_tab for that stock number is A, B, or C, SARSS-GW enters the value from the sig_asl_stock field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is 2. See Note 2.	
		c. If the first position of the SOS field of the amdf_tab for that stock number is A, B, or C, SARSS-GW enters the value from the sig_asl_pa field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is not 2. See Note 2.	
Fund Code	52-53	a. If the MSC fields of the dodaac_tabs for the DODAACs in RP 30-35 of the source A0_ and RP 30-35 of this A4_ are the same, SARSS-GW perpetuates this value from the source A0_, unless it is blank.	
		b. If it is blank and the MSC fields of the dodaac_tabs for the DODAACs in RP 30-35 of the source A0_ and RP 30-35 of this A4_ are the same, SARSS-GW enters the value from the fc_inter_1 field of the msc_tab for the DODAAC in RP 30-35 of the source A0	
		c. If it is blank and the MSC fields of the dodaac_tabs for the DODAACs in RP 30-35 of the source A0_ and RP 30-35 of this A4_ are not the same, SARSS-GW enters the value from the fc_inter_1 field of the msc_tab for the DODAAC in RP 30-35 of this A4	

Table J-24 (Cont.)
A4\_ Non-Dedicated Referral Order to a SARSS1
(Response Code 23)
(Unit-Level Logic)

(Offit-Level Logic)		
Data Element	Record Pos.	Definition/Source
	54-56	SARSS-GW perpetuates this value from the source A0
Project Code	57-59	SARSS-GW enters the Project Code from the abf_tab where the NIIN/qty was found.
	60-66	SARSS-GW perpetuates this value from the source A0
Date RQN received	67-69	This field contains the date the requisition was received at the SARSS-GW (Julian date).
Ownership/ Purpose Code	70	SARSS-GW enters the OPC from the abf_tab record where the NIIN/qty was found.
Condition Code	71	SARSS-GW enters the Condition Code from the abf_tab record where the quantity was found.
Issue indicator	72	SARSS-GW enters a constant 1 for any quantity found above the RO. See Note 3.
Filler	73	This position is blank.
SARSS-GW RIC	74-76	SARSS-GW enters AF4.
Filler	77-80	These positions are blank.
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from the RIC field of the abf_xref_tab of the activity where the quantity was found.
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.

Table J-24 (Cont.)
A4\_ Non-Dedicated Referral Order to a SARSS1
(Response Code 23)
(Unit-Level Logic)

#### Notes:

- 1. The source A0\_ is the one SARSS-GW received from ULLS, SAMS-1, or DS4.
- 2. The supporting SSA is determined from the dodaac\_tab for the DODAAC in RP 30-35. The NIIN in RP 12-22 determines what SSA's abf\_xref\_tab is used, based on the SCMC from the amdf\_tab. All Media and Status Codes, Signal Codes, RICs, and supporting DODAACs will be taken from this table.

SCMC (2nd pos.)	Supporting SSA ABF
Anything	spt_ric_i_vi
Anything	spt_ric_ii_x
Anything	spt_ric_iii
Anything	spt_ric_iv
Anything	spt_ric_v
Anything	spt_ric_vi
Anything	spt_ric_vii
Anything	spt_ric_viii
Α	spt_ric_ixa
L	spt_ric_ixm
Not A or L	spt_ric_ixc
Anything	spt_ric_x
	(2nd pos.)  Anything A

- 3. The SARSS-GW determines the issue\_ind code by the item not being ISM. The code is always 1 for non-ISM items. Issue to the requisitioning objective (RO).
- 4. The SARSS-GW generates this referral order for a SARSS1 supported by another SARSS2AC/B to satisfy an A0\_ received from SARSS2AC/B for a NIIN group that is above the RO in the corps.

Table J-25
A4\_ Referral Order to a SARSS1
(Response Code 23)
(Intermediate-Level Logic)

(Intermediate-Level Logic)			
Data Element	Record Pos.	Definition/Source	
DIC	1-3	SARSS-GW enters A4 in RP 1-2 and perpetuates the value in RP 3 from the source A0 See Note 1.	
RIC	4-6	SARSS-GW enters the value from the ric field of the shipping activity's abf_xref_tab.	
Media and Status Code	7	SARSS-GW perpetuates this value from the source A0	
FSC	8-11	SARSS-GW enters the value of the NIIN in RP 12-24 from the amdf_tab, unless the A0_ states do not substitute, in which case it enters the value from the original A0	
NIIN	12-22	SARSS-GW enters the value from the abf_tab of the RIC where the quantity was located, unless the A0_ states do not substitute, in which case it enters the value from the source A0	
	23-43	SARSS-GW perpetuates this value from the source A0	
Suffix Code	44	SARSS-GW enters A.	
	45-56	SARSS-GW perpetuates this value from the source A0	
Project Code	57-59	SARSS-GW enters the Project Code from the abf_tab where the NIIN/qty was found.	
	60-69	SARSS-GW perpetuates this value from the source A0	
Ownership/ Purpose Code	70	SARSS-GW enters the OPC from the abf_tab record where the NIIN/qty was found.	
Condition Code	71	SARSS-GW enters the Condition Code from the abf_tab record where the quantity was found.	
Issue Indicator Code	72	SARSS-GW enters a constant 1 for any quantity found above the RO.	
	73	This position is blank.	
SARSS-GW RIC	74-76	SARSS-GW enters AF4.	
	75-80	These positions are blank.	

Table J-25 (Cont.)
A4\_ Referral Order to a SARSS1
(Response Code 23)
(Intermediate-Level Logic)

Data Element	Record Pos.	Definition/Source
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from the com_ric_hist field of the abf_xref_tab of the activity where the quantity was found.
SEND-ID-DOW	87-91	SARSS-GW enters the Julian date as YYDDD.

#### Notes:

- 1. The source A0\_ is the one SARSS-GW received from SARSS2AC/B.
- 2. SARSS-GW determines the issue\_ind code by the item not being ISM. The code is always 1 for non-ISM items. Issue to the RO.
- 3. SARSS-GW generates this referral order for a SARSS1 supported by another SARSS2AC/B to satisfy an A0\_ received from SARSS2AC/B for a NIIN group that is above the RO in the corps.

Table J-26
A4\_ Referral Order to SAILS or DS4
(Response Codes 11 and 23)
(Intermediate-Level Logic)

Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW enters A4 in RP 1-2 and perpetuates the value in RP 3 from the source A0
RIC	4-6	SARSS-GW enters the value from the ric field of the shipping activity's abf_xref_tab.
Media and Status Code	7	SARSS-GW perpetuates this value from the source A0
FSC	8-11	SARSS-GW perpetuates this value from the source A0_ if it matches the amdf_tab. If it does not match, SARSS-GW applies the correct FSC from the amdf_tab.
NIIN, UI, Quantity, DODAAC, Date, and SN	12-43	SARSS-GW perpetuates these values from the source A0
Suffix Code	44	SARSS-GW enters A.
Suffix Code  Supplementary address, Signal Code, Fund Code, Distribution Code, Project Code, Priority, RDD, and Advice Code	44 45-69	SARSS-GW enters A.  SARSS-GW perpetuates these values from the source A0
Supplementary address, Signal Code, Fund Code, Distri- bution Code, Project Code, Priority, RDD, and Advice		SARSS-GW perpetuates these values from the source
Supplementary address, Signal Code, Fund Code, Distribution Code, Project Code, Priority, RDD, and Advice Code  Ownership/	45-69	SARSS-GW perpetuates these values from the source A0
Supplementary address, Signal Code, Fund Code, Distribution Code, Project Code, Priority, RDD, and Advice Code  Ownership/Purpose Code	45-69	SARSS-GW perpetuates these values from the source A0  This field is blank.
Supplementary address, Signal Code, Fund Code, Distribution Code, Project Code, Priority, RDD, and Advice Code  Ownership/Purpose Code	70 71	SARSS-GW perpetuates these values from the source A0  This field is blank.  SARSS-GW enters A.

General: SARSS-GW generates this referral order for a SAILS or DS4 to satisfy an A0\_received from SARSS2AC/B.

Note: The source A0\_ is the one SARSS-GW received from SARSS2AC/B.

Table J-27
A4\_ Referral Order to a SAILS or DS4 to Satisfy an A0\_ from SARSS2AC/B
(Response Codes 11 and 23)
(Intermediate-Level Logic)

Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW enters A4 in RP 1-2 and perpetuates the value in RP 3 from the source A0 See Note.
RIC	4-6	SARSS-GW enters the value from the ric_dodaac field of the shipping activity's abf_xref_tab.
Media and Status Code, NSN, UI, Quantity, DODAAC, Date, and SN	7-43	SARSS-GW perpetuates these values from the source A0
Suffix Code	44	SARSS-GW enters A.
Supplementary address, Signal Code, Fund Code, Distribution Code, Project Code, Priority, RDD, and Advice	45-73	SARSS-GW perpetuates these values from the source A0
SARSS-GW RIC	74-76	SARSS-GW enters AF4.
	75-80	These positions are blank.

Note: The source A0\_ is the one SARSS-GW received from SARSS2AC/B.

Table J-28 Supply Status Tr (Initial Status)	ansaction	to DS4
Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW enters the value AE1.
RIC	4-6	SARSS-GW enters the value AF4.
Media and Status Code	7	SARSS-GW perpetuates this value from the source A0 See Note 1.
FSC	8-11	SARSS-GW enters the correct fsc from the fsc field of the amdf_tab for the stock number in RP 8-22 of the source A0_ if the FSC in RP 8-11 of the source A0_ is incorrect.
NIIN, UI, Quantity, DODAAC, Date, and SN	12-43	SARSS-GW perpetuates these values from the source A0
	44	This position remains blank.
Supplementary address, Signal Code, Fund Code, and Distribution Code	45-56	SARSS-GW perpetuates these values from the source A0
Activity Code	57-59	SARSS-GW enters the Activity Code of the supply activity receiving the referral order, or leaves this field blank.
Priority	60-61	SARSS-GW perpetuates this value from the source A0
Status date	62-64	SARSS-GW enters the current date as DDD.
Status Code	65-66	SARSS-GW enters the correct Status Code value.
	67-80	These positions remain blank.

Table J-28 (Cont.) Supply Status Transaction to DS4 (Initial Status)

General: This transaction identifies the correct FSC for the requestor.

#### Notes:

- The source A0\_ is the one SARSS-GW receives from a DS4 user.
- 2. SARSS-GW assigns Status Codes as follows:

Condition Status Code

SARSS-GW passed the request to the supporting SAILS for issue, or generated a referral order to a nonsupport activity.

SARSS-GW passed the request to the supporting SAILS because of controls identified on the SAILS abf tab.

BM

BA

Table J-29 Supply Status Ti	ansaction	to DS4 (Answer to Follow-Up)
Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW enters AE1.
RIC	4-6	SARSS-GW enters AF4.
Media and Status Code	7	SARSS-GW perpetuates this value from the follow-up. See Note 1.
NIIN and UI	8-24	SARSS-GW perpetuates these values from the follow-up.
Quantity	25-29	SARSS-GW enters the quantity in this field.
DODAAC, Date, and SN	30-43	SARSS-GW perpetuates these values from the follow-up.
	44	This position is blank.
Supplementary address, Signal Code, Fund Code, and Distribution Code	45-56	SARSS-GW perpetuates these values from the follow-up.
Activity Code	57-59	SARSS-GW enters the Activity Code of the supply activity receiving the referral order, or leaves this field blank.
Priority	60-61	SARSS-GW perpetuates this value from the follow-up.
Status date	62-64	SARSS-GW enters the current date as DDD.
Status Code	65-66	SARSS-GW enters the correct Status Code value. See Note 2.
	67-80	These positions are blank.

Table J-29 (Cont.)
Supply Status Transaction to DS4 (Answer to Follow-Up)

### Notes:

- 1. The follow-up transaction is the AC\_, AF\_, AK\_, AM\_, or AT\_ SARSS-GW received from DS4.
- 2. Assign Status Codes as follows:

Follow-Up	Condition	Status
AF_, AT_	SARSS-GW generated a referral order for a nonsupport activity.	B5
AC_, AK_	SARSS-GW generated a referral order for a nonsupport activity.	B8
AM_	SARSS-GW generated a referral order for a nonsupport activity.	B2
All	A quantity canceled by a denial from a nonsupport activity.	CS
All	A quantity canceled by lack of response to a referral order.	CA

Table J-30
Status Transaction for ULLS or SAMS-1 Passing Action to DAAS (Response Code 14)
(DS- and Unit-Level Logic)

,	0 /	
Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW enters AE1.
RIC from	4-6	SARSS-GW enters the value AF4.
Media and Status Code, NSN, UI, Quantity, DODAAC, Date, SN, Demand Code, Supplementary address, Signal Code, Fund Code, Distribution Code, Project Code, Priority, and Status date	7-64	SARSS-GW perpetuates these values from the source A0 See Note.
Status Code	65-66	SARSS-GW enters BM.
RIC from	67-69	SARSS-GW enters the value from RP 4-6 of the source A0
	70-71	These positions remain blank.
\$	72	SARSS-GW enters \$. (First refusal/denial.)
SARSS-GW Code	73-80	SARSS-GW perpetuates this value from the source A0
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.
Note: The source	A0_ is the	reformatted A0_ that was uploaded to DAAS.

Table J-31 AE1 with BA Status Transaction from DS4 or SAILS Passed to SARSS2AC/B (Intermediate- and DS-Level Logic)		
Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW perpetuates this value from the incoming status transaction.
RIC	4-6	SARSS-GW perpetuates this value from RP 67-69 of the incoming status transaction.
Media and Status Code	7	SARSS-GW perpetuates this value from RP 7 of the incoming status transaction.
NSN	8-22	a. SARSS-GW perpetuates this value from RP 8-22 of the incoming status transaction if it matches RP 8-22 of the A0_ posted to the trans_hist_tab.
		b. If it does not match, SARSS-GW enters the value in RP 8-22 of the A0_ posted to the trans_hist_tab.
UI, Quantity, DODAAC, Date, SN, Demand Code, Supple- mentary ad- dress, Signal Code, Fund Code, Distri- bution Code, Project Code, Priority, Status date, and Status Code	23-66	SARSS-GW perpetuates these values from RP 23-66 of the incoming status transaction.
RIC	67-69	SARSS-GW perpetuates this value from RP 4-6 of the incoming status transaction.
ESD and Unit price	70-80	SARSS-GW perpetuates these values from RP 70-80 of the incoming status transaction.
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.
SEND-ID-RIC- FR	84-86	SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.
SEND-ID-DOW	87-91	SARSS-GW enters the date as YDDD.

Table J-32
AE1 with BH Status Transaction from DS4 or SAILS Passed as a BA Status to SARSS2AC/B

(Intermediate- and DS-Level Logic)

Data Element Record Pos.  DIC 1-3 SARSS-GW perpetuates this value from the incoming status transaction.  RIC 4-6 SARSS-GW perpetuates this value from RP 67-69 of the incoming status transaction.  7 SARSS-GW perpetuates this value from RP 7 of the incoming status transaction.  NSN 8-22 a. SARSS-GW perpetuates this value from RP 8-22 of the incoming status transaction if it matches RP 8-22 of the AO_ posted to the trans_hist_tab.  b. If it does not match, SARSS-GW enters the value in RP 8-22 of the AO_ posted to the trans_hist_tab.  UI, Quantity, DODAAC, Date, SN, Demand Code, Supplementary address, Signal Code, Fund Code, Fund Code, Fund Code, Project Code, SARSS-GW perpetuates this value from RP 4-6 of the incoming status transaction.  SARSS-GW perpetuates this value from RP 4-6 of the incoming status transaction.  SARSS-GW perpetuates these values from RP 70-80 of the incoming status transaction.  SARSS-GW perpetuates these values from RP 70-80 of the incoming status transaction.  SEND-ID-RIC-FR 81-83 SARSS-GW enters AF4.  SEND-ID-RIC-TO 84-86 SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.  SEND-ID-DOW 87-91 SARSS-GW enters the date as YYDDD.	(IIIIeIIIIeulale- all	u DS-Level	Logic)
RIC 4-6 SARSS-GW perpetuates this value from RP 67-69 of the incoming status transaction.  7 SARSS-GW perpetuates this value from RP 7 of the incoming status transaction.  NSN 8-22 a. SARSS-GW perpetuates this value from RP 8-22 of the incoming status transaction if it matches RP 8-22 of the A0_ posted to the trans_hist_tab.  b. If it does not match, SARSS-GW enters the value in RP 8-22 of the A0_ posted to the trans_hist_tab.  UI, Quantity, DODAAC, Date, SN, Demand Code, Supplementary address, Signal Code, Fund Code, Distribution Code, Project Code, Priority, and Status date  Status Code 65-66 SARSS-GW enters BA.  RIC 67-69 SARSS-GW perpetuates this value from RP 4-6 of the incoming status transaction.  ESD and Unit price SARSS-GW perpetuates these values from RP 70-80 of the incoming status transaction.  SEND-ID-RIC-TR 81-83 SARSS-GW enters be value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.	Data Element		Definition/Source
the incoming status transaction.  7 SARSS-GW perpetuates this value from RP 7 of the incoming status transaction.  8-22 a. SARSS-GW perpetuates this value from RP 8-22 of the incoming status transaction if it matches RP 8-22 of the A0_ posted to the trans_hist_tab.  b. If it does not match, SARSS-GW enters the value in RP 8-22 of the A0_ posted to the trans_hist_tab.  UI, Quantity, DODAAC, Date, SN, Demand Code, Supplementary address, Signal Code, Fund Code, Project Code, Sarss-GW enters BA.  RIC 67-69 SARSS-GW enters BA.  RIC 67-69 SARSS-GW perpetuates this value from RP 4-6 of the incoming status transaction.  ESD and Unit 70-80 SARSS-GW perpetuates these values from RP 70-80 of the incoming status transaction.  SEND-ID-RIC-FR 81-83 SARSS-GW enters AF4.  SEND-ID-RIC-TO 84-86 SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.	DIC	1-3	
incoming status transaction.  NSN  8-22  a. SARSS-GW perpetuates this value from RP 8-22 of the incoming status transaction if it matches RP 8-22 of the AO_ posted to the trans_hist_tab.  b. If it does not match, SARSS-GW enters the value in RP 8-22 of the AO_ posted to the trans_hist_tab.  UI, Quantity, DODAAC, Date, SN, Demand Code, Supplementary address, Signal Code, Fund Code, Distribution Code, Project Code, Priority, and Status date  Status Code  SARSS-GW enters BA.  RIC  67-69  SARSS-GW perpetuates this value from RP 4-6 of the incoming status transaction.  ESD and Unit price  SARSS-GW perpetuates this value from RP 70-80 of the incoming status transaction.  SARSS-GW perpetuates this value from RP 70-80 of the incoming status transaction.  SARSS-GW perpetuates this value from RP 70-80 of the incoming status transaction.  SARSS-GW perpetuates these values from RP 70-80 of the incoming status transaction.  SEND-ID-RIC-FR  81-83  SARSS-GW enters AF4.  SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.	RIC	4-6	· ·
the incoming status transaction if it matches RP 8-22 of the A0_ posted to the trans_hist_tab.  b. If it does not match, SARSS-GW enters the value in RP 8-22 of the A0_ posted to the trans_hist_tab.  UI, Quantity, DODAAC, Date, SN, Demand Code, Supple- mentary address, Signal Code, Fund Code, Distri- bution Code, Project Code, Priority, and Status date  Status Code  65-66  SARSS-GW enters BA.  RIC  67-69  SARSS-GW perpetuates this value from RP 4-6 of the incoming status transaction.  ESD and Unit price  70-80  SARSS-GW perpetuates these values from RP 70-80 of the incoming status transaction.  SEND-ID-RIC-FR  81-83  SARSS-GW enters AF4.  SEND-ID-RIC-TO  84-86  SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.		7	
UI, Quantity, DODAAC, Date, SN, Demand Code, Supplementary address, Signal Code, Fund Code, Distribution Code, Project Code, Priority, and Status date  Status Code 65-66 SARSS-GW enters BA.  RIC 67-69 SARSS-GW perpetuates this value from RP 4-6 of the incoming status transaction.  ESD and Unit price 70-80 SARSS-GW perpetuates these values from RP 70-80 of the incoming status transaction.  SEND-ID-RIC-FR 81-83 SARSS-GW enters AF4.  SEND-ID-RIC-TO 84-86 SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.	NSN	8-22	the incoming status transaction if it matches RP 8-22 of the A0_ posted to the trans_hist_tab.  b. If it does not match, SARSS-GW enters the value in
RIC 67-69 SARSS-GW perpetuates this value from RP 4-6 of the incoming status transaction.  ESD and Unit price SARSS-GW perpetuates these values from RP 70-80 of the incoming status transaction.  SEND-ID-RIC-FR 81-83 SARSS-GW enters AF4.  SEND-ID-RIC-TO 84-86 SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.	DODAAC, Date, SN, Demand Code, Supple- mentary address, Signal Code, Fund Code, Distri- bution Code, Project Code, Priority, and	23-64	
incoming status transaction.  ESD and Unit 70-80 SARSS-GW perpetuates these values from RP 70-80 of the incoming status transaction.  SEND-ID-RIC-FR 81-83 SARSS-GW enters AF4.  SEND-ID-RIC-TO 84-86 SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.	Status Code	65-66	SARSS-GW enters BA.
price the incoming status transaction.  SEND-ID-RIC-FR 81-83 SARSS-GW enters AF4.  SEND-ID-RIC-TO 84-86 SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.	RIC	67-69	
SEND-ID-RIC-TO 84-86 SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.		70-80	
the dodaac_tab for the DODAAC in RP 30-35.	SEND-ID-RIC-FR	81-83	SARSS-GW enters AF4.
SEND-ID-DOW 87-91 SARSS-GW enters the date as YYDDD.	SEND-ID-RIC-TO	84-86	
	SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.

# Table J-33

AE1 with CB Status Transaction Blank Suffix Code (Refusal) or Suffix Code not Blank (First Denial) from DS4 or A4\_ 1R or 1S from SAILS Passed as a BM Status to SARSS2AC/B

(Intermediate- and DS-Level Logic)

	T =	5 /
Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW perpetuates this value from the incoming status transaction.
RIC	4-6	SARSS-GW enters AF4.
Media and Status Code	7	SARSS-GW perpetuates this value from RP 7 of the incoming status transaction.
NSN	8-22	<ul> <li>a. SARSS-GW perpetuates this value from RP 8-22 of the incoming status transaction if it matches RP 8-22 of the A0_ posted to the trans_hist_tab.</li> <li>b. If it does not match, SARSS-GW enters the value in RP 8-22 of the A0_ posted to the trans_hist_tab.</li> </ul>
UI	23-24	SARSS-GW perpetuates this value from the incoming status transaction.
Quantity	25-29	SARSS-GW perpetuates this value from the refusal/denial transaction, unless the quantity is greater than the rfo_qty. If the quantity is greater, SARSS-GW enters the rfo_qty.
DODAAC, Date, SN, Demand Code, Supplementary address, Signal Code, Fund Code, Distribution Code, Project Code, Priority, and Status date	30-64	SARSS-GW perpetuates this value from the incoming status transaction.
Status Code	65-66	SARSS-GW enters BM.
RIC	67-69	SARSS-GW enters this value from the SOS field of the amdf_tab for the NSN in RP 8-22.

Table J-33 (Cont.)

AE1 with CB Status Transaction Blank Suffix Code (Refusal) or Suffix Code not Blank (First Denial) from DS4 or A4\_ 1R or 1S from SAILS Passed as a BM Status to SARSS2AC/B

(Intermediate- and DS-Level Logic)

Data Element	Record Pos.	Definition/Source
	70-71	These positions are blank.
\$	72	SARSS-GW enters \$.
	73	This position is blank.
ESD and Unit price	74-80	SARSS-GW perpetuates these values from RP 70-80 of the incoming status transaction.
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.

# Table J-34

AE1 with CB Status Transaction (First Denial) from DS4 or an A4\_ 1R or 1S from SAILS Passed as a C\* Status to SARSS2AC/B (Intermediate- and DS-Level Logic)

`		
Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW perpetuates this value from the incoming status transaction.
RIC	4-6	SARSS-GW enters AF4.
Media and Status Code	7	SARSS GW perpetuates this value from RP 7 of the incoming status transaction.
NSN	8-22	<ul> <li>a. SARSS-GW perpetuates this value from RP 8-22 of the incoming status transaction if it matches RP 8-22 of the A0_ posted to the trans_hist_tab.</li> <li>b. If it does not match, SARSS-GW enters the value in RP 8-22 of the A0_ posted to the trans_hist_tab.</li> </ul>
UI	23-24	SARSS-GW perpetuates this value from the incoming status transaction.
Quantity	25-29	SARSS-GW perpetuates this value from the refusal/denial transaction, unless the quantity is greater than the rfo_qty. If the quantity is greater, SARSS-GW enters the rfo_qty.
DODAAC, Date, SN, Demand Code, Supplementary address, Signal Code, Fund Code, Distribution Code, Project Code, Priority, and Status date	30-64	SARSS-GW perpetuates this value from the incoming status transaction.
Status Code	65-66	SARSS-GW enters C*.
RIC	67-69	SARSS-GW perpetuates this value from RP 4-6 of the AE1 with CB status transaction from DS4.
	70-73	These positions are blank.

Table J-34 (Cont.)

AE1 with CB Status Transaction (First Denial) from DS4 or an A4\_ 1R or 1S from SAILS Passed as a C\* Status to SARSS2AC/B (Intermediate- and DS-Level Logic)

Data Element	Record Pos.	Definition/Source
ESD and Unit price	74-80	SARSS-GW perpetuates these values from RP 70-80 of the incoming status transaction.
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.

# Table J-35

AE1 with CB Status Transaction (Subsequent Denial) from DS4 or an A4\_ 1R or 1S from SAILS Passed as a CM Status to SARSS2AC/B (Intermediate- and DS-Level Logic)

`		
Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW perpetuates this value from the incoming status transaction.
RIC	4-6	SARSS-GW enters AF4.
Media and Status Code	7	SARSS-GW perpetuates this value from RP 7 of the incoming status transaction.
NSN	8-22	<ul> <li>a. SARSS-GW perpetuates this value from RP 8-22 of the incoming status transaction if it matches RP 8-22 of the A0_ posted to the trans_hist_tab.</li> <li>b. If it does not match, SARSS-GW enters the value in RP 8-22 of the A0_ posted to the trans_hist_tab.</li> </ul>
		RP 8-22 of the A0_ posted to the trans_hist_tab.
UI	23-24	SARSS-GW perpetuates this value from the incoming status transaction.
Quantity	25-29	SARSS-GW perpetuates this value from the refusal/denial transaction, unless the quantity is greater than the rfo_qty. If the quantity is greater, SARSS-GW enters the rfo_qty.
DODAAC, Date, SN, Demand Code, Supplementary address, Signal Code, Fund Code, Distribution Code, Project Code, Priority, and Status date	30-64	SARSS-GW perpetuates this value from the incoming status transaction.
Status Code	65-66	SARSS-GW enters CM.
RIC	67-69	SARSS-GW perpetuates this value from RP 4-6 of the AE1 with CB status transaction from DS4.
	70-73	These positions are blank.

Table J-35 (Cont.)

AE1 with CB Status Transaction (Subsequent Denial) from DS4 or an A4\_ 1R or 1S from SAILS Passed as a CM Status to SARSS2AC/B (Intermediate- and DS-Level Logic)

Data Element	Record Pos.	Definition/Source
ESD and Unit price	74-80	SARSS-GW perpetuates these values from RP 70-80 of the incoming status transaction.
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.

Table J-36
SARSS-GW-Created AE1 Status Transaction Answer to an AC\_ or AK\_ from SARSS2AC/B and Downloaded to SARSS2AC/B
(Intermediate-Level Logic)

Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW enters AE1.
RIC	4-6	SARSS-GW enters AF4.
	7-64	SARSS-GW perpetuates these values from RP 7-64 of the AC_ or AK
Status Code	65-66	SARSS-GW enters B8.
RIC	67-69	SARSS-GW enters AF4
ESD and Unit price	70-80	SARSS-GW perpetuates these values from RP 70-80 of the AC_ or AK
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from the com_ric_hist field on the dodaac_tab for the DODAAC in RP 30-35
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.

Table J-37

SARSS-GW-Created AE1 Status Transaction Answer to an AC\_ or AK\_ from SARSS2AC/B and Downloaded to SARSS2AC/B (AC\_ or AK\_ Reformatted and Uploaded to DAAS)

(Intermediate-Level Logic)

Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW enters AE1.
RIC FROM	4-6	SARSS-GW enters AF4.
	7-64	SARSS-GW perpetuates these values from RP 7-64 of the AC_ or AK
Status Code	65-66	SARSS-GW enters BM.
RIC	67-69	SARSS-GW enters the value from the SOS field of the amdf_tab for the stock number in RP 8-22.
	70-80	SARSS-GW perpetuates these values from RP 70-80 of the AC_ or AK
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from the com_ric_hist field on the dodaac_tab for the DODAAC in RP 30-35.
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.

Table J-38

SARSS-GW-Created AE1 Status Transaction Answer to an AM\_ from SARSS2AC/B and Downloaded to SARSS2AC/B

(Intermediate-Level Logic)

Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW enters AE1.
RIC	4-6	SARSS-GW enters AF4.
	7-64	SARSS-GW perpetuates these values from RP 7-64 of the AM
Status Code	65-66	SARSS-GW enters B2.
RIC	67-69	SARSS-GW enters AF4.
	70-80	SARSS-GW perpetuates these values from RP 70-80 of the AM
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from the com_ric_hist field on the dodaac_tab for the DODAAC in RP 30-35.
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.

Table J-39

SARSS-GW-Created AE1 Status Transaction Answer to an AM\_ from SARSS2AC/B and Downloaded to SARSS2AC/B (AM\_ Reformatted and Uploaded to DAAS) (Intermediate-Level Logic)

Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW enters AE1.
RIC from	4-6	SARSS-GW enters AF4.
	7-64	SARSS-GW perpetuates these values from RP 7-64 of the AM
Status Code	65-66	SARSS-GW enters BM.
RIC	67-69	SARSS-GW enters the value from the SOS field of the amdf_tab for the stock number in RP 8-22.
	70-80	SARSS-GW perpetuates these values from RP 70-80 of the AM
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from the com_ric_hist field on the dodaac_tab for the DODAAC in RP 30-35.
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.

Table J-40
SARSS-GW-Created AE1 Status Transaction Answer to an AF\_ or AT\_ from SARSS and Downloaded to SARSS2B
(Intermediate-Level Logic)

Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW enters AE1.
	4-24	SARSS-GW perpetuates the value from RP 4-24 of the AF_ or AT
Quantity	25-29	Determined by SARSS-GW logic.
	30-64	SARSS-GW perpetuates these values from RP 30-64 of the AF_ or AT
Status Code	65-66	Determined by SARSS-GW logic.
RIC from	67-69	Determined by SARSS-GW logic.
	70-80	SARSS-GW perpetuates these values from RP 70-80 of the AF_ or AT
SEND-ID-RIC- FR	81-83	SARSS-GW RIC (AF4)
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from the com_ric_hist field on the dodaac_tab for the DODAAC in RP 30-35.
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.

Table J-41

Status Transaction for A4\_ Dedicated Referral to Another Activity

(Response Codes 11 and 13)

(DS- and Unit-Level Logic)

Data Element	Record Pos.	Definition/Source	
DIC	1-3	SARSS-GW enters AE1.	
RIC from	4-6	SARSS-GW enters the value AF4.	
	7-43	SARSS-GW perpetuates these values from the A4	
Suffix Code	44	This field is blank	
	45-61	SARSS-GW perpetuates these values from the A4	
Transaction date	62-64	SARSS-GW enters the date as DDD.	
Status Code	65-66	SARSS-GW enters BD.	
RIC from	67-69	SARSS-GW enters the value from RP 4-6 of the AF4.	
Estimated shipping date	70-73	SARSS-GW enters the date as YDDD.	
	74-80	These positions are blank.	
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.	
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.	
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.	
0 1 0 1 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0			

General: SARSS-GW creates and downloads this transaction to SARSS2B when a referral order is generated to satisfy an A0\_ from a DS4, ULLS, or SAMS-1 supported by SARSS.

# Table J-42

AC\_ or AK\_ in Conjunction with an AC\_ or AK\_ from SARSS2AC/B and Reformatted by SARSS-GW and Uploaded to DAAS (Intermediate-Level Logic)

Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW perpetuates this value from RP 1-3 of the AC_ or AK received from SARSS2AC/B.
RIC		SARSS-GW enters the value from the SOS field of the amdf_tab for the stock number in RP 8-22.
		SARSS-GW perpetuates these values from RP 7-66 of the AC_ or AK_ received from SARSS2AC/B.
RIC	67-69	SARSS-GW perpetuates this value from RP 4-6 of the AC_ or AK_ received from SARSS2AC/B.
	70-80	SARSS-GW perpetuates these values from RP 70-80 of the AC_ or AK_ received from SARSS2AC/B.

Table J-43

 ${\rm AM\_}$  in Conjunction with an  ${\rm AM\_}$  from SARSS2AC/B and Reformatted and Uploaded to DAAS

(Intermediate-Level Logic)

Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW perpetuates this value from RP 1-3 of the AM_ received from SARSS2AC/B.
RIC	4-6	SARSS-GW enters the value from the SOS field of the amdf_tab for the stock number in RP 8-22.
	7-66	SARSS-GW perpetuates these values from RP 7-66 of the AM_ received from SARSS2AC/B.
RIC	67-69	SARSS-GW perpetuates this value from RP 4-6 of the AM_ received from SARSS2AC/B.
	70-80	SARSS-GW perpetuates these values from RP 70-80 of the AM_ received from SARSS2AC/B.

Table J-44 AS1 Created from BA Status Transaction Passed to SARSS2AC/B (DS-Level Logic)		
Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW enters AS1.
RIC	4-56	SARSS-GW perpetuates these values from RP 4-56 of the output BA status transaction.
Date shipped	57-59	SARSS-GW perpetuates this value from RP 71-73 of the output BA status transaction.
	60-61	SARSS-GW perpetuates these values from RP 60-61 of the output BA status transaction.
TCN	62-76	SARSS-GW perpetuates these values from RP 30-43 of the output BA status transaction to RP 62-75 and enters X in RP 76.
	77	SARSS-GW perpetuates this value from RP 77 of the incoming status transaction.
Date available for shipment	78-80	SARSS-GW perpetuates this value from RP 71-73 of the output BA status transaction.
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.

Table J-45
SARSS-GW-Created AS\_ Shipment Status Transaction Answer to an AF\_ or AT\_
from SARSS and Downloaded to SARSS2B
(Intermediate-Level Logic)

Data Element	Record Pos.	Definition/Source	
DIC	1-3	SARSS-GW enters AS	
RIC from	4-6	SARSS-GW perpetuates the value from RP 67-69 of the AF_ or AT	
	7-24	SARSS-GW perpetuates these values from RP 7-24 of the AF_ or AT	
Quantity	25-29	Determined by SARSS-GW logic.	
	30-64	SARSS-GW perpetuates these values from RP 30-64 of the AF_ or AT	
Status Code	65-66	SARSS-GW enters SARSS2AC/B.	
RIC from	67-69	SARSS-GW enters AF4.	
	70-80	SARSS-GW perpetuates these values from RP 70-80 of the AF_ or AT	
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.	
SEND-ID-RIC- TO	84-86	SARSS-GW enters the SARSS RIC.	
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.	

Table J-46

YAM SARSS Due-In/Dedicated Due-In Transaction for a DS4, ULLS, or SAMS-1 Referral Action to Another Activity

(Response Code 11, 23, or 45)

(DS- and Unit-Level Logic)

	(CC since comments and comments are comments are comments and comments are comments and comments are comments are comments and comments are comments are comments and comments are comments are comments and comments are comments are comments are comments are comments and comments are comments are comments and comments are comments are comments and comments are comments are comments are comments are comments and comments are comments			
Data Element	Record Pos.	Definition/Source		
DIC	1-3	SARSS-GW enters YAM.		
RIC to	4-6	SARSS-GW enters AF4.		
Media and Status Code	7	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank. See Note 1.		
		b. If it is blank, SARSS-GW enters the value from the supporting SSA's abf_xref_tab media_cd_nsl field. See Note 2.		
FSC	8-11	SARSS-GW perpetuates this value from the source A0_ if it matches the amdf_tab. If it does not match, SARSS-GW applies the correct FSC from the amdf_tab.		
NIIN and UI	12-24	SARSS-GW perpetuates these values from the source A0		
Quantity	25-29	<ul><li>a. SARSS-GW perpetuates this value from the source A0_ for Response Codes 11 and 23.</li><li>b. SARSS-GW enters the quantity found for Response</li></ul>		
		Code 45.		
DODAAC, Date, and SN	30-43	SARSS-GW perpetuates these values from the source A0		
Demand Code	44	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.		
		b. If it is blank, SARSS-GW enters R.		
Supplementary address	45-50	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.		
		b. If it is blank, SARSS-GW enters the user's prime support SSA DODAAC. See Note 3.		

Table J-46 (Cont.)

YAM SARSS Due-In/Dedicated Due-In Transaction for a DS4, ULLS, or SAMS-1 Referral Action to Another Activity

(Response Code 11, 23, or 45)

(DS- and Unit-Level Logic)

Data Flancia	Daniel	Definition/Orange
Data Element	Record Pos.	Definition/Source
Signal Code	51	a. If the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not A, B, or C, SARSS-GW enters the value from the sig_ded_funded field of the requesting activity's dodaac_tab, or if the sig_ded_funded field is blank, SARSS-GW enters the value from the sig_nsl_stock field of the supporting SSA's abf_xref_tab.
		b. If the first position of the SOS field of the amdf_tab for that stock number is A, B, or C, SARSS-GW enters the value from the sig_ded_funded field of the requesting activity's dodaac_tab if the second position of the matcat field of the amdf_tab is 2, or if the sig_ded_funded field is blank, SARSS-GW will enter the value from the sig_nsl_stock field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is 2.  c. If the first position of the SOS field of the amdf_tab for that stock number is A, B, or C, SARSS-GW enters the value from the sig_ded_pa field of the requesting activity's dodaac_tab if the second position of the matcat field of the amdf_tab is not 2, or if the sig_ded_funded field is blank, SARSS-GW enters this value from the sig_nsl_pa field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is not 2.
Fund Code	52-53	a. SARSS-GW perpetuates this value from the source A0_, unless it is blank.
		b. If it is blank, SARSS-GW enters the value from the fc_inter_1 field of the msc_tab for the DODAAC in RP 30-35.
Distribution Code, Project Code, Priority, Status date, and Status Code	54-66	SARSS-GW perpetuates these values from the source A0
	67-68	SARSS-GW enters the fc_ext_1 from the msc_tab from the MILSBILLS Fund Code.

Table J-46 (Cont.)

YAM SARSS Due-In/Dedicated Due-In Transaction for a DS4, ULLS, or SAMS-1 Referral Action to Another Activity

(Response Code 11, 23, or 45)

(DS- and Unit-Level Logic)

Data Element	Record Pos.	Definition/Source
	69-80	These positions remain blank.
SEND-ID-RIC-FR	81-83	SARSS-GW enters AF4.
SEND-ID-RIC-TO	84-86	SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.

General: SARSS-GW generates this transaction to create a dedicated due-in at SARSS for a referral order to satisfy an A0\_ received from a DS4, ULLS, or SAMS-1 supported by SARSS, and the A0\_ meets the dedicated rule.

#### Notes:

- 1. The source A0\_ is the one SARSS-GW received from DS4, ULLS, or SAMS-1.
- 2. The supporting SSA from the dodaac\_tab for the DODAAC in RP 30-35 is determined by the aimi\_tab if the NIIN in RP 12-22 matches an entry and the intermediate support is SARSS, or by the first two positions of the SCMC field of the amdf\_tab for the NIIN in RP 12-22 as follows:
- a. If the NIIN in RP 12-22 matches an entry on the aimi\_tab and the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is not blank, SARSS-GW uses the spt\_ric\_aimi SSA ABF.
- b. If the NIIN in RP 12-22 matches an entry on the aimi\_tab but the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is blank, or the NIIN in RP 12-22 does not match an entry on the aimi\_tab, SARSS-GW uses the first two positions of the scmc field of the amdf\_tab for the NIIN in RP 12-22 to determine the supporting SSA ABF as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting SSA ABF
1	Anything	spt_ric_i_vi
2	Anything	spt_ric_ii_x
3	Anything	spt_ric_iii
4	Anything	spt_ric_iv
5	Anything	spt_ric_v
6	Anything	spt_ric_i_vi
7	Anything	spt_ric_vii
8	Anything	spt_ric_viii

Table J-46 (Cont.)

YAM SARSS Due-In/Dedicated Due-In Transaction for a DS4, ULLS, or SAMS-1 Referral Action to Another Activity

(Response Code 11, 23, or 45)

(DS- and Unit-Level Logic)

Notes: (Cont.)

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting SSA ABF
9	Α	spt_ric_ixa
9	Ĺ	spt_ric_ixm
9	Not A or L	spt_ric_ixc
0	Anvthina	spt ric ii x

- 3. SARSS-GW determines the transaction DODAAC using one of three methods.
- a. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SIC value from the sic field of the abf\_tab as follows:

SIC	DSU Code	Supporting DODAAC
Α	F	ssa_ixa
С	Α	ssa_ixc
F	K	ssa_iv
J	K	ssa_iii
M	Н	ssa_ixm
T	K	ssa_vii
U	K	ssa_ii_x

b. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV and the sic field is blank or there is no abf\_tab record, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by converting the value in the scmc field of the amdf\_tab to a SIC value. SARSS-GW then converts the SIC value to a DSU Code as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	SIC	DSU Code	Supporting DODAAC	
1	Anything	U	K	ssa_i_vi	
2	Anything	T	K	ssa_ii_x	
3	Anything	J	K	ssa_iii	
4	Anything	F	K	ssa_iv	
5	Anything	U	K	ssa_v	
6	Anything	U	K	ssa_i_vi	
7	Anything	T	K	ssa_vii	
8	Anything	С	Α	ssa_viii	
9	Α	Α	F	ssa_ixa	

Table J-46 (Cont.)

YAM SARSS Due-In/Dedicated Due-In Transaction for a DS4, ULLS, or SAMS-1 Referral Action to Another Activity

(Response Code 11, 23, or 45)

(DS- and Unit-Level Logic)

Notes:	(Cont.)
140100.	( OOI 11. <i>)</i>

SCMC (1st pos.)	SCMC (2nd pos.)	SIC	DSU Code	Supporting DODAAC
9	L	М	Н	ssa_ixm
9	Not A or L	С	Α	ssa_ixc
0	Anything	U	K	ssa_ii_x

c. If the typ field of the abf\_xref\_tab for the supporting SSA is not DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SCMC value from the amdf\_tab for the stock number in RP 8-22 as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting DODAAC
1	Anything	ssa_i_vi
2	Anything	ssa_ii_x
3	Anything	ssa_iii
4	Anything	ssa_iv
5	Anything	ssa_v
6	Anything	ssa_i_vi
7	Anything	ssa_vii
8	Anything	ssa_viii
9	Α	ssa_ixa
9	L	ssa_ixm
9	Not A or L	ssa_ixc
0	Anything	ssa_ii_x

Table J-47 YDO to a SARSS1 (Response for Referral) (Intermediate- and Unit-Level Logic) Data Element Record Definition/Source Pos. DIC 1-3 SARSS-GW enters YDO. **RIC** 4-6 SARSS-GW enters AF4. 7-24 SARSS-GW perpetuates this value from the A0 . SARSS-GW perpetuates this value from the AE with Quantity 25-29 BA/BH status. SARSS-GW perpetuates this value from the source Document 30-43 number Suffix Code 44 SARSS-GW perpetuates this value from the AE with BA/BH status. 45-66 SARSS-GW perpetuates this value from the source A0\_. Filler 67-73 RIC ship 74-76 SARSS-GW perpetuates this value from RP 4-6 of the AE\_ with BA status. (Before RP 4-6 and 67-69 are

Note: The source A0\_ is the one SARSS-GW received from SARSS2AC/B. This is the A0\_ in the A0\_ data field of the trans\_hist\_tab.

number.

switched, input AE\_BA.)

These positions are blank.

SARSS-GW enters the value from the com ric hist field

of the RIC-TO-DODAAC in RP 30-35 for the document

SARSS-GW enters the Julian date as YYDDD.

SARSS-GW enters AF4.

Filler

FR

TO

SEND-ID-RIC-

SEND-ID-RIC-

SEND-ID-DOW

77-80

81-83

84-86

87-91

Table J-48
YAL Due-In and Due-Out Transaction for a Referral Action to Another Activity
(Response Code 11)
(Unit-Level Logic)

Data Flamont	Docord	Definition/Course	
Data Element	Record Pos.	Definition/Source	
DIC	1-3	SARSS-GW enters YAL.	
RIC-TO	4-6	SARSS-GW enters AF4.	
Media and Status Code	7	SARSS-GW enters the value from the media_cd_asl field of the supporting SSA's abf_xref_tab. See Note 1.	
FSC	8-11	SARSS-GW perpetuates this value from the source A0_ if it matches the amdf_tab. If it does not match, SARSS-GW applies the correct FSC from the amdf_tab. See Note 2.	
NIIN, UI, and Quantity	12-29	SARSS-GW perpetuates these values from the source A0	
DODAAC	30-35	SARSS-GW enters the user's prime support SSA DODAAC. See Note 3.	
Date	36-39	SARSS-GW enters the date as YDDD.	
Serial number	40-43	SARSS-GW uses the docreg field of the supporting SSA's dodaac_tab to determine what serial number to enter, as follows:	
		RP 40 is X, V, or Z. RP 41-43 is the next available sequence number, beginning with 001 each day.	
Supplementary	45-50	a. SARSS-GW enters Y in RP 45.	
address		b. SARSS-GW enters Y in RP 46 if the SLC on the supporting ABF for the stock number in RP 8-22 is not Z. If it is Z, SARSS-GW enters W.	
		c. SARSS-GW enters W in RP 47.	
		d. Position 48 is blank.	
		e. SARSS-GW enters the fc_ext_1 from the msc_tab for the MILSBILLS Fund Code.	

Table J-48 (Cont.)
YAL Due-In and Due-Out Transaction for a Referral Action to Another Activity (Response Code 11)

(Unit-Level Logic)

Data Element	Record Pos.	Definition/Source
Signal Code	51	a. If the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is not A, B, or C, SARSS-GW enters the value from the sig_asl_stock field of the supporting SSA's abf_xref_tab.
		b. If the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is A, B, or C, SARSS-GW enters the value from the sig_asl_stock field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is 2.
		c. If the first position of the SOS field of the amdf_tab for the stock number in RP 8-22 of the source A0_ is A, B, or C, SARSS-GW enters the value from the sig_asl_pa field of the supporting SSA's abf_xref_tab if the second position of the matcat field of the amdf_tab is not 2.
Fund Code	52-53	SARSS-GW enters the value from the fc_inter_1 field of the msc_tab for the DODAAC in RP 30-35.
Distribution Code, Project Code, Priority, Status date, and Advice Code	54-66	SARSS-GW perpetuates these values from the source A0
DON	67-80	SARSS-GW perpetuates this value from RP 30-43 of the original A0
SEND-ID-RIC- FR	81-83	SARSS-GW enters AF4.
SEND-ID-RIC- TO	84-86	SARSS-GW enters the value from the com_ric_hist field of the dodaac_tab for the DODAAC in RP 30-35.
SEND-ID-DOW	87-91	SARSS-GW enters the date as YYDDD.

Table J-48 (Cont.)

YAL Due-In and Due-Out Transaction for a Referral Action to Another Activity (Response Code 11)

(Unit-Level Logic)

General: SARSS-GW generates this transaction to create a non-dedicated due-in and due-out at SARSS for a referral order to satisfy an A0\_ received from ULLS or SAMS-1 that is supported by SARSS and that meets the non-dedicated rule.

#### Notes:

- 1. The supporting SSA from the dodaac\_tab for the DODAAC in RP 30-35 is determined by the aimi\_tab if the NIIN in RP 12-22 matches an entry and the intermediate support is SARSS, or by the first two positions of the SCMC field of the amdf\_tab for the NIIN in RP 12-22 as follows:
- a. If the NIIN in RP 12-22 matches an entry on the aimi\_tab and the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is not blank, SARSS-GW uses the spt\_ric\_aimi SSA ABF.
- b. If the NIIN in RP 12-22 matches an entry on the aimi\_tab but the com\_ric\_hist field of the dodaac\_tab for the DODAAC in RP 30-35 is blank, or the NIIN in RP 12-22 does not match an entry on the aimi\_tab, SARSS-GW uses the first two positions of the scmc field of the amdf\_tab for the NIIN in RP 12-22 to determine the supporting SSA ABF as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting SSA ABF
1	Anything	spt_ric_i_vi
2	Anything	spt_ric_ii_x
3	Anything	spt_ric_iii
4	Anything	spt_ric_iv
5	Anything	spt_ric_v
6	Anything	spt_ric_i_vi
7	Anything	spt_ric_vii
8	Anything	spt_ric_viii
9	Α	spt_ric_ixa
9	L	spt_ric_ixm
9	Not A or L	spt_ric_ixc
0	Anything	spt_ric_ii_x

2. The source A0 is the one SARSS-GW received from DS4, ULLS, or SAMS-1.

Table J-48 (Cont.)

YAL Due-In and Due-Out Transaction for a Referral Action to Another Activity (Response Code 11) (Unit-Level Logic)

Notes: (Cont.)

- 3. SARSS-GW determines the transaction DODAAC using one of three methods.
- a. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SIC value from the sic field of the abf\_tab as follows:

SIC	DSU Code	Supporting DODAAC
Α	F	ssa_ixa
С	Α	ssa_ixc
F	K	ssa_iv
J	K	ssa_iii
M	Н	ssa_ixm
Τ	K	ssa_vii
U	K	ssa_ii_x

b. If the typ field of the abf\_xref\_tab for the supporting SSA is DN or DV and the sic field is blank or there is no abf\_tab record, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by converting the value in the scmc field of the amdf\_tab to a SIC value. SARSS-GW then converts the SIC value to a DSU Code as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	SIC	DSU Code	Supporting DODAAC
1 2 3 4 5 6 7 8 9 9	Anything Anything Anything Anything Anything Anything Anything Anything Anything A	U T J F U U T C A M C U	K K K K K K A F H A K	ssa_i_vi ssa_ii_x ssa_iii ssa_iv ssa_v ssa_vii ssa_viii ssa_viii ssa_ixa ssa_ixm ssa_ixc ssa_ii_x

Table J-48 (Cont.)

YAL Due-In and Due-Out Transaction for a Referral Action to Another Activity (Response Code 11) (Unit-Level Logic)

Notes: (Cont.)

c. If the typ field of the abf\_xref\_tab for the supporting SSA is not DN or DV, SARSS-GW determines the DODAAC in RP 30-35 or 45-50 by the SCMC value from the amdf\_tab for the stock number in RP 8-22 as follows:

SCMC (1st pos.)	SCMC (2nd pos.)	Supporting DODAAC
1	Anything	ssa_i_vi
2	Anything	ssa_ii_x
3	Anything	ssa_iii
4	Anything	ssa_iv
5	Anything	ssa_v
6	Anything	ssa_i_vi
7	Anything	ssa_vii
8	Anything	ssa_viii
9	Α	ssa_ixa
9	L	ssa_ixm
9	Not A or L	ssa_ixc
0	Anything	ssa_ii_x

Table J-49 Demand Transaction (DHA) SAILS (Referral Order to a Nonsupporting SAILS) (DS- and Unit-Level Logic) Data Element Record Definition/Source Pos. DIC 1-3 SARSS-GW enters DHA. RIC 4-6 SARSS-GW enters the value from the ric field of the supporting SAILS abf\_xref\_tab. 7 This position is blank. NSN, UI, SARSS-GW perpetuates these values from the source 8-50 Quantity, A0\_. DODAAC, Date, SN. Demand Code, and Supplementary address 51-53 These positions are blank. EIC 54-56 SARSS-GW perpetuates this value from the source A0\_. 57-59 These positions are blank. SARSS-GW perpetuates this value from the source **Priority** 60-61 designator A0\_. 80 This position remains blank.

General: This transaction records the demand at the supporting SAILS activity.

Note: The source A0\_ is the one SARSS-GW received to create an RFO for a non-supporting SAILS activity with the same fin\_comri as the support SAILS.

Table J-50 ABF Extract Record from SAILS or DS4		
Data Element	Record Pos.	Definition/Source
Stock key	1-11	This field contains NIIN/PN/MCN extracts. See Note.
Stockage List Code	12	SARSS-GW extracts this value from the Stockage List Code field of the DS4 ABF. This field is blank on SAILS ABF extract records.
Distribution of Stockage Code	13	SARSS-GW extracts this value from the Distribution of Stockage Code field of the DS4 ABF and from the Edit Code field of the SAILS ABF.
Freeze Code	14	SARSS-GW extracts this value from the Freeze Code field of the DS4 ABF and from the Inventory Flag Code field of the SAILS ABF.
RO	15-19	This is the cumulative value extracted from the requisitioning objective fields of the DS4 and SAILS ABF.
ROP	20-24	This is the cumulative value extracted from the reorder point fields of the DS4 and SAILS ABF.
Safety level	25-29	This is the cumulative value extracted from the safety level fields of the DS4 and SAILS ABF.
Qty on hand	30-34	This is the cumulative value extracted from the on-hand serviceable quantity fields of the DS4 and SAILS ABF.
Due-in qty	5-39	This is the cumulative value extracted from the due-in quantity fields of the DS4 and SAILS ABF.
Due-out qty	40-44	This is the cumulative value extracted from the due-out quantity fields of the DS4 and SAILS ABF.
Qty on hand	45-49	This is the cumulative value extracted from the on-hand unserviceable quantity fields of the DS4 and SAILS ABF.
Manager Code	50-51	SARSS-GW extracts this value from the Manager Code field of the SAILS ABF.
SIC	50	SARSS-GW extracts this value from the Special Interest Code field of the DS4 ABF.
	51	This field is blank on records extracted from the DS4 ABF.

Table J-50 (Cont.) ABF Extract Record from SAILS or DS4		
Data Element	Record Pos.	Definition/Source
ITC	52	SARSS-GW extracts this value from the Item Control Code field of the SAILS ABF. This field is blank on records extracted from the DS4 ABF.
Local Supply Source Code	53	SARSS-GW extracts this value from the Local Supply Source Code field of the SAILS ABF. This field is blank on records extracted from the DS4 ABF.
Key Depot RIC	54-56	SARSS-GW extracts this value from the Key Depot RIC field of the SAILS ABF. This field is blank on records extracted from DS4 ABF.

General: The X22ALB File is the data source for SAILS. The A57AGL ABF File is the data source for DS4.

Note: To identify the NIIN, part number, and manager control number, record positions 10 and 11 include ON, blank, P, or OM, respectively.

Table J-51 ABF Extract Record from SARSS (YSB)		
Data Element	Record Pos.	Definition/Source
DIC	1-3	YSB
RIC-STOR-SITE	4-6	This the RIC of the SSA that relates to this ABF.
NIIN	7-17	This is the NIIN of the item listed on the ABF.
OWN-PURP-CD	18	This tells who owns the item and for what purpose.
PROJ-CD	19-21	This identifies items for specific projects.
COND-CD	22	This tells the condition of the item.
QTY-RO	23-29	This is the SSA's RO.
QTY-RP	30-36	This is the SSA's RP.
QTY-SL	37-40	This is the SSA's SL.
QTY-OH	41-47	This is how much of an item the SSA has.
QTY-DI	48-54	This is the materiel due in for the SSA.
QTY-DO	55-61	This is the materiel due out from the SSA.
STKG-CD	62	This tells what type of item it is and whether it is demand-supported.
INV-FREEZE- FL	63	This tells whether the item is on hold pending inventory.
SIC	64	For DS4 only, this is the Special Interest Code.
TYP-STKNO- CD	65	This identifies a NIIN, CAGE, or part number.
KEY-DEPOT- RIC	66-68	For SAILS only.
EDIT-CD	69	For SAILS only.
MGR-CD	70-71	For SAILS only.
LOC-SUP-SRC- CD	72	For SAILS only.
ICC/DSC/CDC	73	This is the SAILS Item Control Code, DS4 Distribution of Stockage Code, or SARSS Control Degree Code.
TIME	74-79	HHMMSS

Table J-51 (Cont.) ABF Extract Record from SARSS (YSB)		
Data Element	Record Pos.	Definition/Source
ACTION-CD	80	This will contain P for partial (daily) or T for total (complete).
SEND-ID-RIC- FR	81-83	This the RIC of the SSA that is shipping the item.
SEND-ID-RIC- TO	84-86	This is the RIC of the SSA that is receiving the item.
SEND-ID-DOW	87-91	This is the date the transaction was written.

Table J-52 SARSS-GW-Created YIC Due-In from a Retrograde Transaction (The Denial/Issue Release Confirmation Process will generate DIC YIC for confirmed shipment of excess being shipped to another SARSS1.)

Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW enters YIC.
RIC-TO	4-6	This is the Routing Identifier Code of the receiver.
Filler	7	This position is blank.
FSC	8-11	This is the federal supply classification.
NIIN	12-22	This is the national item identification number.
UI	23-24	This is the unit of issue.
QTY	25-29	This is the transaction quantity.
DODAAC	30-35	This is the Department of Defense Activity Address Code.
DOC-DTE	36-39	This is the document date.
DOC-SERL	40-43	This is the document serial number.
SUFIX-CD	44	This is the Suffix Code.
SUPPL-ADRS- CD	45-50	This is the Supplementary Address Code.
SIG-CD	51	This is the Signal Code.
FC	52-53	This is the Fund Code.
RIC-STOR-SITE	54-56	This is the RIC of the SARSS1 storage site.
COND-CD	57	This is the Condition Code.
TCN	60-76	This is the transportation control number.
MODE-OF-SHP	77	This is the mode of shipment.
POE	78-80	This is the port of embarkation.
SEND-ID-RIC- FR	81-83	This is the RIC of the sender.
SEND-ID-RIC- TO	84-86	This is the RIC of the receiver.
SEND-ID-DOW	87-91	This is the date the transaction was written.

#### Table J-53

SARSS-GW-Created DIC YIL, Follow-Up to a Retrograde Shipment Transaction (When the RETRO-SW on the SARSS1 Unit Unique Record is Y, a DIC YIL will be generated and sent to the Transaction-Out File [TOF]. An image of the YIL will also be sent to the SARSS1 Manager Error List.)

Data Element	Record Pos.	Definition/Source
DIC	1-3	SARSS-GW enters YIL.
RIC-TO	4-6	This is the Routing Identifier Code of the receiver.
COND-CD	7	This is the Condition Code.
FSC	8-11	This is the federal supply classification.
NIIN	12-22	This is the national item identification number.
UI	23-24	This is the unit of issue.
QTY	25-29	This is the transaction quantity.
DODAAC	30-35	This is the Department of Defense Activity Address Code.
DOC-DTE	36-39	This is the document date.
DOC-SERL	40-43	This is the document serial number.
SUFIX-CD	44	This is the Suffix Code.
SUPPL-ADRS- CD	45-50	This is the Supplementary Address Code.
SIG-CD	51	This is the Signal Code.
FC	52-53	This is the Fund Code.
RIC-STOR-SITE	54-56	This is the RIC of the SARSS1 storage site.
PROJ-CD	57-59	This is the Project Code.
TCN	60-76	This is the transportation control number.
Filler	77-80	These positions are blank.
SEND-ID-RIC- FR	81-83	This is the RIC of the sender.
SEND-ID-RIC- TO	84-86	This is the RIC of the receiver.
SEND-ID-DOW	87-91	This is the date the transaction was written.

Blank Page